

GOTHAM

A modern, minimal-ish, versatile and extendable theme for Beamer

Romain NOEL
romainoel@free.fr

v1.2.0.a — 2024-11-11

Contents

1	Introduction	2
2	Getting Started	3
2.1	Installing from CTAN	3
2.2	Installing from Gitlab	3
2.3	A Minimal Example	4
2.4	Dependencies	4
3	Customization	5
3.1	Package options	5
3.1.1	Font theme	6
3.1.2	Color theme	7
3.1.3	Inner theme	7
3.1.4	Outer theme	9
3.2	Setup all the options	13
3.3	Frame options	14
3.4	Commands for Customization	15

3.5	Color Customization	18
3.6	Font Customization	18
3.6.1	Old style figures	19
3.7	Length Customization	19
4	Tips & Tricks	21
4.1	Backup Slides	21
4.2	Sources of inspiration	22
5	Known Issues	22
5.1	Title formats	22
5.2	Interactions with other color themes	23
5.3	Notes on second screen	23
5.4	Standout frames with labels	24
5.5	Standout frames with Pandoc	24
5.6	Other issues	25
6	License	25
7	Commands description for users	26
8	Package implementation for developers	41
Change History		205

1 Introduction

Beamer is an awesome way to make presentations with L^AT_EX, but its theme selection is surprisingly sparse. The stock themes share an aesthetic that can be a little cluttered, while the few distinctive custom themes available are often specialized for a particular corporate or institutional brand.

The goal of **Gotham** is to provide a simple, modern Beamer theme suitable for anyone to use. It tries to minimize noise and maximize space for content; some visual flourishes are offered as options.

The final product provides a modern, elegant and versatile theme with a high degree of customization. So it can easily be used to build a particular corporate or institutional brand theme on top of it.

The implementation of this theme is strongly inspired from the excellent **METROPOLIS** theme by Matthias Vogelgesang, from which it borrows numerous options. **Gotham**'s codebase lives on [Gitlab](#).

If you have issues, find mistakes in the manual or want to help make the theme even better, please get in touch there. Any feature request, issue report or merge requests are welcome.

2 Getting Started

2.1 Installing from CTAN

The latest stable version of **Gotham** is available on **CTAN** and should now be part of the usual **T_EX** distributions (**T_EX Live**, **MacT_EX** , **MikT_EX**), under the name *beamertHEME-gotham*. It means that if your distribution is kept up-to-date, the package should normally be already installed on your system. If this is not the case, consider updating the packages of your Tex distribution.

For **T_EX Live** and **MacT_EX** users, this usually means running

```
tlmgr update --all
```

or if administrative privileges are required

```
sudo tlmgr update --all
```

For **MikT_EX** users, please refer to [the official MikT_EX documentation](#).

2.2 Installing from Gitlab

If you want to use the cutting-edge development version of **Gotham**, you can install it manually by following these steps:

Download the source from [Gotham repository](#) using `git clone` or as a `zip` archive of the latest development version.

Compile the style files by running `l3build unpack` inside the downloaded directory.
(Or run **L^AT_EX** directly on `source/gothamtheme.ins`.)

Move the resulting `*.sty` files to the folder containing your presentation. To use **Gotham** with many presentations, run `l3build install` or move the `*.sty` files

to a folder in your T_EX path instead.

Use the **theme** by declaring `\usetheme{gotham}` in the preamble of your document.

Gotham uses the l3build system to offer the following installation options for advanced users:

`l3build unpack` builds the theme style files.

`l3build doc` builds this documentation manual and the examples.

`l3build check` builds the theme and manual.

`l3build clean` removes the files generated by `l3build`.

`l3build install` installs the theme into your local texmf folder.

`l3build uninstall` removes the theme from your local texmf folder.

2.3 A Minimal Example

The following code shows a minimal example of a Beamer presentation using **Gotham**, and the output generated is given on fig. 1.

```
\documentclass{beamer}
\usetheme{gotham} % Loads Gotham theme
\title{A minimal example}
\subtitle{using Gotham theme}
\date{\today}
\author{John DOE}
\institute{Your university or company}

\begin{document}
\maketitle
\section{First Section}
\begin{frame}{First Frame}
Hello world !
\end{frame}
\end{document}
```

2.4 Dependencies

Gotham depends on the `beamer` class and the following standard packages:

- `tikz`



Figure 1: A simple example.

- `expl3`
- `xfp`
- `etoolbox`
- `ifxetex`
- `ifluatex`

For best results, we recommend installing the fonts `Fira Sans` and `Fira Mono` and compiling with **Gotham** using XeLaTeX or LuaTeX. These are optional dependencies; **Gotham** is compatible with (e.g.) pdfL^AT_EX and will fall back to standard fonts if `Fira Sans` or `Fira Mono` is not installed.

The packaged name of `Fira Sans` is `Fira Sans OT` in some Linux distributions; this case is automatically handled by **Gotham**.

3 Customization

3.1 Package options

Gotham provides a number of options, which can be set using a key=value interface. The primary way to set options is to provide a comma-separated list of option-value pairs when loading **Gotham** in the preamble:

```
\usetheme[option1=value1, option2=value2, ...]{gotham}
```

Options can be changed at any time — even mid-presentation ! — with the \gothamset command.

```
\gothamset{option1=newvalue1, option2=newvalue2, ...}
```

The list of options is structured as shown in the following example.

option key	<i>list of possible values</i>	default: default
	A short description of the option.	

As **Gotham** implementation is heavily inspired from the excellent **METROPOLIS** theme by Matthias Vogelgesang, many of METROPOLIS options are also available in **Gotham**.

3.1.1 Font theme

format title	<i>regular, lower, upper, titlecase</i>	default: regular
format subtitle	Individually controls the format/case of titles, subtitles, frametitle, framesubtitles, part, section and subsection titles.	
format framesubtitle		
format part		
format section		
format subsection		
shape title	<i>regular, italic, smallcaps</i>	default: regular
shape subtitle	Individually controls the shape/series of titles, subtitles, frametitle, framesubtitles, part, section and subsection titles.	
shape frametitle		
shape framesubtitle		
shape part		
shape section		
shape subsection		

FRAMETITLE OF A FRAME

Subtitle frame

(a) Example
 format frametitle=titlecase,
 shape frametitle=smallcaps,
 format framesubtitle= lower,
 shape framesubtitle=regular.

frametitle of a frame

Subtitle frame

(b) Example of format frametitle=lower,
 shape frametitle=italic,
 format framesubtitle= regular,
 shape framesubtitle=italic.

Figure 2: Examples of format and shape settings.

3.1.2 Color theme

The included **Gotham** color theme is used by default, but its colors can be easily changed to suit your tastes. All of the theme's styles are defined in terms of a few main colors:

- `colorA` The primary theme color, used for frametitle, standout and text if the appropriate options are selected.

An easy way to customize the theme is to redefine these colors using:

```
\colorlet{colorPale}{gPaleYell} % BG in light/normal mode
\colorlet{colorDark}{gDarkBlack} % FG in light/normal mode
\colorlet{colorA}{gDarkTeal} % frametitle, standin.out,
\colorlet{colorAreversed}{gLightTeal} % frametitle, standin.in,
\colorlet{colorB}{gMidGrey} % gray BG : progress bar, blocks
\colorlet{colorC}{gDeepYellow} % progress bar
\colorlet{colorD}{gLightOrange} % alert
\colorlet{colorE}{gLightGreen} % example
```

`background` *light, dark, transparent* default: transparent

Controls weather the color of all headings (title page, frame title, etc.) should be in black (`default`) or in a slightly darker shade of the theme color `theme`.

`colorset` *red, anthracite* default: anthracite

Predefined set colors (`colorA, colorB, ...`) leading to different ambiances.

`block` *native, transparent, fill* default: native

Optionally adds a light grey background to block environments like `theorem` and `example`.

3.1.3 Inner theme

`title page` *gotham normal, gotham reversed, gotham dividedpic, gotham splitvert, <your-name>* default: gotham normal

By setting this option you can change the title page according predefined style or even set your own template. If you want to use your own template, this latter should be previously defined with: `\defbeamertemplate{title page}{<your-name>}{<your-defintion>}`

<code>watermark default</code>	<code>on, off</code> default: off
Enable or disable the watermark background template by default (ie. without using <code>\begin{frame}[watermark]</code>).		
<code>watermark template</code>	<code>gotham draft, <your-name></code> default: gotham draft
Set the watermark background template to use when the <code>watermark</code> option is activated (by default or locally). If you want to use your own template, this latter should be previously defined with: <code>\defbeamertemplate{background}{watermark/<your-name>}{<your-defintion>}</code> .		
<code>standin template</code>	<code>gotham, <your-name></code> default: gotham
<code>standout template</code>	Set the standin and stantout template to use when the <code>standin</code> or <code>stantout</code> frame option is activated. If you want to use your own template, this latter should be previously defined with: <code>\defbeamertemplate{standout}{<your-name>}{<your-defintion>}</code> .	
<code>standin BG template</code>	<code>gotham, <your-name></code> default: gotham
<code>standout BG template</code>	Since most of the time the standin and standout are only varying from their backgrounds, Gotham offers the possibility to change only and simply these local background through this option. This option sets the standin and stantout background template to use when the <code>standin</code> or <code>stantout</code> frame option is activated. If you want to use your own template, this latter should be previously defined with: <code>\defbeamertemplate{background}{standin/<your-name>}{<your-defintion>}</code> .	
<code>partframe default</code>	<code>on, off</code> default: on
<code>sectionframe default</code>	Enable or disable the display of the part frame (section, subsection and subsubsection respectively) at each part (other respectively) increment.	
<code>subsectionframe default</code>		
<code>subsubsectionframe default</code>		
<code>partframe template</code>	<code>gotham progressbar, gotham simple, gotham splitvert progressbar, gotham splitvert simple, gotham progressvert</code> default: gotham progressbar
<code>sectionframe template</code>		
<code>subsectionframe template</code>		
<code>subsubsectionframe template</code>	Set the frame template to use when the <code>part</code> (or <code>section</code> , <code>subsection</code> , <code>subsubsection</code> respectively) frame option is activated (ie. using <code>\begin{frame}[part]</code>). If you want to use your own template, before giving its name to this option, your template should be defined with: <code>\defbeamertemplate{part frame}{<your-name>}{<your-defintion>}</code> .	

`tocframe template gotham simple, gotham bullet, <your-name>` default: gotham bullet

Set the table of contents template to use when the `toc` option is activated. If you want to use your own template, this latter should be previously defined with:

```
\defbeamertemplate{part in toc}{<your-name>}{<your-defintion>}
\defbeamertemplate{section in toc}{<your-name>}{<your-defintion>}
\defbeamertemplate{subsection in toc shaded}{<your-name>}{{<your-defintion>}}
\defbeamertemplate{subsubsection in toc shaded}{<your-name>}{{<your-defintion>}}
\defbeamertemplate{background canvas}{toc/<your-name>}{<your-definition>}
\defbeamertemplate{toc page}{<your-name>}{<your-defintion, set them now by exmaple>}
```

`parttocframe default on, off` default: on

`sectiontocframe default` Enable or disable the display of the table of content frame after the part frame (section,

`subsectiontocframe default` subsection and subsubsection respectively) at each part (other respectively) increment.

`subsubsectiontocframe default`

`parttocframe template gotham simple, gotham bullet, <your-name>` default: gotham bullet

`sectiontocframe template` Set the frame template to use when the table of contents at each new `part` (or `section`,

`subsectiontocframe template` subsection, `subsubsection` respectively). This new frame is internally using the `tocpart` frame option to activate the frame template. If you want to use your own template, before giving its name to this option, your template should be defined with:

```
\defbeamertemplate{part frame}{<your-name>}{<your-defintion>}.
```

3.1.4 Outer theme

`sidebar canvas right template gotham filigrane, empty, <your-name>` default: gotham filigrane

`sidebar canvas left template` Setting templates for left and right sidebar canvas which are activated when giving the

frame option `\begin{frame}[edging]`. If you want to use your own template, before giving its name to this option, your template should be defined with: `\defbeamertemplate{sidebar canvas right}{default/<your-name>}{<your-defintion>}`

`edging default on, off` default: off

The option `edging default=on` can enable the `sidebar canvas right` (and `sidebar canvas left`) templates on every frame; but it can still be turned off for specific frames when using the frame option `\begin{frame}[noedging]`.

`frametitle template gotham subsameline, gotham subnewline, <your-name>` default: gotham subsameline

Option to set the frametitle template. **Gotham** offers one template that adds the subtitle on the same line (`gotham-subsameline`) and one that adds the subtitle on a new line (`gotham-subnewline`). If you want to use your own template, before giving its name to this option, your template should be defined with: `\defbeamertemplate{frametitle}{default/<your-name>}{<your-defintion>}`

`framesubtitle template gotham subnewline, <your-name>` default: gotham subnewline

Setting the template to use when the subtitle is on a new line. If you want to use your own template, before giving its name to this option, your template should be defined with: `\defbeamertemplate{framesubtitle}{default/<your-name>}{<your-defintion>}`

`frametitle continuation gotham, beamer, tot, <your-name>` default: gotham

`template` Setting the template that is used in the frametitle when a frame too long and is continued/broke into several frames (using the frame option `allowframebreaks`). If you want to use your own template, before giving its name to this option, your template should be defined with: `\defbeamertemplate{frametitle continuation}{default/<your-name>}{<your-defintion>}`

`numbering none, framenumber, totalframenumber, appendixframenumber, pagenumber, totalpagenumber, circle` default: none

Setting the template with the frame number at the bottom right of each slide.

`footer template gotham, <your-name>` default: gotham

Setting the template that appears in the footer of the frame. `gotham` footer print the `shortdate` at right, the `shorttitle` in the middle and the `shortauthor` at left. Since in 16/9 the height is precious, `gotham` template also offers the possibility to rotate `shortdate` and `shortauthor` so they appear on sides. If you want to use your own template, before giving its name to this option, your template should be defined with: `\defbeamertemplate{frame footer}{default/<your-name>}{<your-defintion>}`

```
rotateFooter default on, off..... default: off
```

Enable or disable the `rotateFooter` frame option by default (ie. without using `\begin{frame}[rotateFooter]` on every frame). If the option is activated, it can be deactivated locally using the frame option `\begin{frame}[noRotateFooter]`.

```
mini frames shape default (bullet from beamer), tick, box, gotham minibullet, gotham box, gotham minibox, <your-name>..... default: gotham minibullet
```

Setting the shape of the mini frames to use, if the mini frame bundle refers to it (which is usually the case). If you want to use your own template, before giving its name to this option, your template should be defined with:

```
\defbeamertemplate{mini frame}{<your-name>}{
  <your-defintion>
}[action]{
  \setbeamersize{mini frame size=.1cm, mini frame offset=.05
    cm}
}
\defbeamertemplate{mini frame in current subsection}{<your-
  name>}{
  <your-defintion>
}
```

`mini frames bundle gotham mini, beamer, gotham nano <your-name>` default: gotham mini

Setting the set of symbols used in the mini frame navigation. If you want to use your own template, before giving its name to this option, your template should be defined with:

```
\defbeamertemplate{miniframe~home}{<your-name>}{<your-def>}
\defbeamertemplate{miniframe~current~slide}{<your-name>}{<
    your-def>}
\defbeamertemplate{miniframe~done~current~section}{<your-name
    >}{<your-def>}
\defbeamertemplate{miniframe~todo~current~section}{<your-name
    >}{<your-def>}
\defbeamertemplate{miniframe~done~other~section}{<your-name
    >}{<your-def>}
\defbeamertemplate{miniframe~todo~other~section}{<your-name
    >}{<your-def>}
\defbeamertemplate{miniframe~part}{<your-name>}{<your-def>}
\defbeamertemplate{miniframe~section~current}{<your-name>}{<
    your-def>}
\defbeamertemplate{miniframe~section~done}{<your-name>}{<your
    -def>}
\defbeamertemplate{miniframe~section~todo}{<your-name>}{<your
    -def>}
\defbeamertemplate{miniframe~subsection~current}{<your-name
    >}{<your-def>}
\defbeamertemplate{miniframe~subsection~todo}{<your-name>}{<
    your-def>}
\defbeamertemplate{miniframe~subsection~done}{<your-name>}{<
    your-def>}
```

`mini frames compress on, off` default: on

A shortcut for the beamer option `compress` that affects the mini frames.

`mini frames nav spreading spreading, centering, left, right` default: spreading

Controls how the mini frame should spread in the navigation bar.

`mini frames nav sectioning none, section, secsubsection` default: none

Setting the `section` in head/foot template that is used on top of the mini frame navigation bar.

```
mini frames nav position none, head, foot, left, right ..... default: none
```

Setting where the mini frame navigation bar should appear.

```
progressbar position none, head, frametitle, foot, circlehead, left, right ..... default: none
```

Setting where the progressbar should appear. The different positions are pretty obvious from their name, except for `circlehead`. This latter option is putting a circular progressbar around the frametitle-logo (from frametitle template defined with gotham theme). It worth noting that by doing so, the frametitle is using the command `\gothamInstituteLogoCircle` instead of `\gothamInstituteLogoSquare` which is used otherwise.

```
progressbar style rectangle, rounded box, moving circle, fixed circle ..... default: rectangle
```

Setting how the progressbar should appear. `rectangle` option is using sharp rectangle for the progressbar, while `rounded box` is using rounded box and adds the percentage of progression at its right. `moving circle` and `fixed circle` are concerning the option `progressbar position=circle` only. `moving circle` add the number of the frame in a circle moving (following) the progression of the bar, while `fixed circle` put this framenumber constantly at the right of the circular progressbar.

```
progressbar advancement tlbr, brtl ..... default: tlbr
```

Defines in which direction the progressbar should evolve. `tlbr` is the shortcut for: starting from the top left corner, it goes bottom then right, ie. anti-clockwise. `brtl` is the shortcut for: starting from the bottom right corner, it goes top then left, ie. clockwise.

```
progressbar mfn on, off ..... default: off
```

Enable or disable the display of the mini frame navigation bar within the progressbar.

3.2 Setup all the options

```
\gothamset{  
    % from font theme  
    format title, shape title,  
    format subtitle, shape subtitle,  
    format frametitle, shape frametitle,  
    format framesubtitle, shape framesubtitle,  
    format part, shape part,  
    format section, shape section,  
    format subsection, shape subsection,  
    % from color theme  
    background,
```

```

block,
colorset,
% from inner theme
title page,
watermark template, watermark default,
standout template, standin template,
standout BG template, standin BG template,
partframe template, partframe default,
sectionframe template, sectionframe default,
subsectionframe template, subsectionframe default,
subsubsectionframe template, subsubsectionframe default,
tocframe template,
parttocframe template, parttocframe default,
sectiontocframe template, sectiontocframe default,
subsectiontocframe template, subsectiontocframe default,
%subsubsectiontocframe template, subsubsectiontocframe
    default,
% from outer theme
sidebar canvas right template, sidebar canvas left
    template,
edging default,
frametitle template, framesubtitle template, frametitle
    continuation template,
numbering,
rotateFooter default,
footer template,
mini frames shape, mini frames bundle, mini frames
    compress, mini frames nav spreading,
progressbar position, progressbar style, progressbar
    advancement, progressbar mfn,
}

```

3.3 Frame options

Frame options are affecting the templates used on the current frame through the following syntax:

```
\begin{frame}[option] ... \end{frame}
```

Below a description of the different frame options brought by **Gotham**.

`noBGC` Apply an empty `background canvas` template.

`watermark` Apply (with `watermark`) or deactivated (`nowatermark` when `\gothamset{watermark nowatermark default=on}` was given) the `background` template, through `\defbeamertemplate {background}{watermark/<your-name>}{<your-def>}` and `\gothamset{watermark template=<your-name>}`.

`standout` Apply the `standin` (and `standout` respectively) templates through the definition `\standin \defbeamertemplate{standin}{<your-name>}{<your-def>}` and the option `\gothamset {standin BG template=<your-name>}`.

`toc` Apply the `toc` template defined by `\gothamset{tocframe template=<your-name>}`.

`edging` Apply (with `edging`) or deactivated (`noedging` when `\gothamset{edging default=on noedging }` was given) the `sidebar canvas left` (and right respectively) template, through `\defbeamertemplate{sidebar canvas left}{default/<your-name>}{<your-def>}` (and right) and the option `\gothamset{sidebar canvas left template=<your-name>}` (and right).

`nologo` Apply empty `logo` (and `footline`, `footer` respectively) templates. This can be convenient when extra space is needed.

`nofooter`

`rotateFooter` Enable or disable the rotation of the elements in the `footer`. This can be convenient when extra space is needed in 16/9 mode especially.

`part` Apply `\usebeamertemplate{part frame}`, (`section frame`, `subsection frame` and `section subsubsection frame` respectively) templates. This makes more sense for internal use, `subsec` but can be reused everywhere else.

`subsubsec`

`tocpart` Apply `\usebeamertemplate{toc part frame}`, (`toc section frame`, `toc subsection frame`, `tocsec` and `toc subsubsection frame` respectively) templates. This makes more sense for internal use, `tocsubsec` but can be reused everywhere else.

`tocsubsubsec`

3.4 Commands for Customization

Gotham defines some commands that can be used as hooks, ie., that can be redefined when needed.

```
\gothamInstituteLogoCircle[1][4ex]
```

#1 : height of the picture.

Command to include the circular logo of your institute in the frametitle when using `\gothamset{progressbar position=circlehead}`. For example, you redefine this command through:

```
\renewcommand{\gothamInstituteLogoCircle}[1][4ex]{
    \includegraphics[height=#1]{<your-logo-circular>}
}
```

```
\gothamInstituteLogoSquare[1][4ex]
```

#1 : height of the picture.

Command to include the circular logo of your institute in the frametitle. For example, you redefine this command through:

```
\renewcommand{\gothamInstituteLogoSquare}[1][4ex]{
    \includegraphics[height=#1]{<your-logo-square>}
}
```

`\gothamFrameSubtitleSep` Command defining the separator used between the frametitle and the subtitle.

`\gothamRightFiligrane` Commands that are used by default in the `sidebar canvas right` (and left). This avoids
`\gothamLeftFiligrane` the redefinition of the whole templates, especially since the `sidebar canvas right` is containing elements by default in Beamer theme (like the `logo`).

`\gothamtitlepagelogo` The command to insert the institute logo(s) on title page. For example, you redefine this command through:

```
\renewcommand{\gothamtitlepagelogo} {
    \includegraphics[height=#1]{<your-logo-on-titlepage>}
}
```

`\gothamtitlepagebg` The command to insert the background title page. For example, you redefine this command through:

```
\renewcommand{\gothamtitlepagebg}{  
    \includegraphics[height=#1]{<your-background-on-titlepage>}  
}
```

`\partContentName` `\secContentName` `\subsecContentName` The command to change the title of frames containing part (or section or subsection) table of contents. For example, you redefine this command through:

```
\renewcommand{\partContentName}{Part's agenda}
```

`gothamZeroSectionframes` Boolean variable to flag if they are frame in a zeroth section. This variable helps to adapt the spreading of `mini frames` nav bar. This variable is automatically set if the spread is set correctly at the beginning of the presentation. If the spreading or the mini frame nav is disable at the zeroth section then reactivated latter, it might create unwanted spreading. In such situation the variable has to be set manually to correct the spreading. You change its value with `\booltrue{gothamZeroSectionframes}`.

`darkBG` `transparentBG` A boolean variables that are true with the background mode. It can be useful when you want to apply different codes according to the background you are on. You can use it as in the following example:

```
\ifbool{darkBG}{code to apply on dark background}{other code  
for light or transparent backgrounds}
```

`\gothamHookFooter` The command to add elements (like a logo) in the footer without redefining it completely. For example, you redefine this command through:

```
\renewcommand{\gothamHookFooter}{  
    \usebeamertemplate{instituteLogo}  
}
```

<code>\gothamHookPostColorBGSet</code>	The command to change the colors that are related to the background color setting (ie. frametitle, standin, standout and titlepage). For example, you redefine this command through:
--	--

```
\renewcommand{\gothamHookPostColorBGSet}{  
    \colorlet{colorFrametitle}{yourColor}  
    \colorlet{colorStandout}{yourColor}  
    \colorlet{colorStandin}{yourColor}  
    \colorlet{colorTitlepage}{yourColor}  
    \setbeamercolor{frametitle}{fg=yourRed, bg=}  
}
```

3.5 Color Customization

The included **Gotham** color theme is used by default, but its colors can be easily changed to suit your tastes. All of the theme's styles are defined in terms of three Beamer colors:

- `normal text` (dark fg, light bg)
- `alerted text` (colored fg, should be visible against dark or light)
- `example text` (colored fg, should be visible against dark or light)

An easy way to customize the theme is to redefine these colors using

```
\setbeamercolor{ ... }{ fg= ... , bg= ... }
```

in your preamble. For greater customization, you can redefine any of the other stock Beamer colors. In addition to the stock colors the theme defines a number of **Gotham** specific colors, which can also be redefined to your liking.

```
\setbeamercolor{progress bar}{ ... }  
\setbeamercolor{title separator}{ ... }  
\setbeamercolor{progress bar in head/foot}{ ... }  
\setbeamercolor{progress bar in section page}{ ... }
```

3.6 Font Customization

The default font for **Gotham** is **Fira**. This can be easily changed using the standard font selection commands of the `fontspec` package. So if you prefer, for example, the **Ubuntu** font family, just add the following two commands after loading the **Gotham** theme.

```
\setsansfont{Ubuntu}
\setmonofont{Ubuntu Mono}
```

If you are expecting to present in a large room or with an underpowered projector, you may want to change the font to a heavier weight of Fira to maximize readability.

```
\setsansfont[BoldFont={Fira Sans SemiBold}]{Fira Sans Book}
```

3.6.1 Old style figures

The regular `fontspec` mechanism for changing glyph appearance also applies to this theme. If you want to have old style figures in the text but regular lined figures for math, you could add the following to your preamble:

```
\usefonttheme{professionalfonts} % required for
      mathspec
\usepackage{mathspec}
\setsansfont[BoldFont={Fira Sans},
      Numbers={OldStyle}]{Fira Sans Light}
\setmathsf{Digits}[Numbers={Lining, Proportional}]{Fira Sans Light}
```

3.7 Length Customization

```
\gothamFrametitleToppadding
\gothamFrametitleBottompadding
\gothamFrametitleLeftpadding
\gothamFrametitleRightpadding
```

Lengths controlling the padding around the frametitle.

```
\gothamFramesubtitleStrutend
```

Lengths controlling the padding around the frametitle.

`\sidebarRightHOffset` Length controling the horizontal and vertical offset in order to position `\gothamRightFiligrane`
`\sidebarLeftHOffset` (respectively `\gothamLeftFiligrane`) when using the default sidebar canvas (right and left) from **Gotham**.

```
\gothamFootlineRuleLeftPadding  
\gothamFootlineRuleHeight  
\gothamFootlineRuleLength
```

`\gothamFootlineRuleLeftPadding` is controlling the horizontal space between the left border of the page and the left side of the rule. `\gothamFootlineRuleHeight` controls the height and `\gothamFootlineRuleLength` the length of the rule used to delimit the footer.

```
\gothamFootlineHRightOffset  
\gothamFootlineVOffset  
\gothamFootlineHeight  
\gothamFootlineDepth
```

`\gothamFootlineHRightOffset` is controlling the horizontal space between the right border of the page and the side of the footline. `\gothamFootlineVOffset` is controlling space between to bottom of the text (or the footnote) and the footline. `\gothamFootlineHeight` and `\gothamFootlineDepth` are controlling the height and depth of the footline baseline.

```
\gothamLeftFooterPadding  
\gothamRightFooterPadding  
\gothamFooterHOffset
```

`\gothamLeftFooterPadding` is controlling the horizontal space between the left border of the page and the side of the footer. `\gothamRightFooterPadding` is controlling the horizontal space between the right the footer and the page number. `\gothamFooterHOffset` is controlling the horizontal space between the footer and the bottom of the page (or the progressbar).

```
\gothamHposLeftRotFooter  
\gothamHposRightRotFooter  
\gothamVposLeftRotFooter  
\gothamVposRightRotFooter
```

```
\gothamProgressCircHeight  
\gothamCounterCircleRadius  
\gothamProgressCircBorderWidth
```

Lengths that are controlling the horizontal and vertical positioning of the left and right elements of the rotated footer.

Lengths controlling the aspect of `progress circle`. `\gothamProgressCircHeight` is controlling the inner height of the circle (related to its diameter). `\gothamCounterCircleRadius` is controlling the size of the counter circle containing the frame number. `\gothamProgressCircBorderWidth` is controlling width of the progress circle.

```
\gothamProgressHeadFootLineheight
```

`\gothamProgressHeadFootLineheight` is controlling the height of the progress bar in normal frames (or its width when it is put in side bars).

```
\gothamCircleNumberingVshift
```

```
\gothamCircleNumberingHshift
```

Lengths controlling the vertical and horizontal positioning of the `circle` frame numbering template.

```
\sectionhoffset
```

```
\gothamProgressSectionHeight
```

`\sectionhoffset` controls the horizontal offset of the (section title + progress bar) block. Can be useful when extra stuff wants to be displayed on sides of the block. The default value is 0pt.

`\gothamProgressSectionHeight` controls the height of the progress bar used in part/- section/subsection/subsubsection frames (when progress bar are used).




Figure 3: The layout used by **Gotham**.

4 Tips & Tricks

4.1 Backup Slides

Speakers will often include extra slides at the end of their presentation to refer to during audience questions. One easy way to do this is to include the `appendixnumberbeamer` package in your preamble and call `\appendix` before your backup slides.

Gotham will automatically turn off slide numbering for slides in the appendix.

4.2 Sources of inspiration

Many Beamer themes have been used as sources of inspiration to build **Gotham**:

- <https://github.com/matze/mtheme> for dark/light theme and standout page.
- <https://github.com/hamaluiik/Beamer-Theme-Execushares> and <https://github.com/pcafrica/focus-beamertheme> for titlepage and section-page.
- <https://github.com/LukasPietzschmann/awesome-beamer> for titlepage.
- <https://github.com/luistar/unina-beamer/tree/master> and <https://github.com/jkjaer/aauLatexTemplates/tree/master/aauBeamer/aausimple> for circlehead progress bar.
- <https://github.com/povanberg/flux-beamer> for toc.
- <https://github.com/fliptanedo/FlipBeamerTheme> for numbering circled fraction.
- https://gitlab.com/RomainNOEL/latex3_template_pkg for LaTeX3 template.

5 Known Issues

5.1 Title formats

Be aware that not every font supports small caps, so the `smallcaps` or `upper` options may not work if you use a font other than **Fira Sans**. In particular, the Computer Modern sans-serif typeface, which is used when **Gotham** is compiled with pdfLATEX, does not have a small-caps variant.

The title format options `upper` and `smallcaps` are quite nice from an aesthetic point of view, but their use of `\MakeLowercase` and `\MakeUppercase` can cause unexpected problems. For example:

- Some commands, like `\text{}`, do not work inside `\MakeLowercase` and `\MakeUppercase`. (See [#125](#))
- Only alphabetic characters are affected by `\MakeLowercase`, so numerals and punctuation remain at full height. This can spoil some of the aesthetic benefits of `upper`. (See [#33](#))
- `\MakeLowercase` and `\MakeUppercase` apply to math mode and `\scshape` does not. This can easily introduce mathematical errors that are hard to catch.
- It is impossible to typeset symbols which are encoded as uppercase letters in a different font. In particular, `\mathbb{}` and `\mathcal{}` letters will be replaced by

other math glyphs. (See #153)

The `smallcaps` and `upper` options are safe to use if your titles contain only alphabetic characters and do not require the expansion of any macros.

5.2 Interactions with other color themes

Gotham can be used along with any other Beamer color theme, such as `crane` or `seahorse`. If you wish to do this, it is usually best to include the **Gotham** subpackages individually so the **Gotham** color theme is never loaded. This will prevent conflicts between the **Gotham** color theme and your preferred theme.

For example, overriding the color theme as follows may not work as expected because `\usetheme{gotham}` loads the **Gotham** color theme, which defines a relationship between the frametitle background and the primary palette of the theme. Since `seahorse` assumes a different relationship between its palettes, the result is a grey, rather than periwinkle, frametitle background.

```
\usetheme{gotham}  
\usecolortheme{seahorse}
```

The correct colors are chosen if the **Gotham** outer, inner, and font themes are loaded separately:

```
\useoutertheme{gotham}  
\useinnertheme{gotham}  
\usefonttheme{gotham}  
\usecolortheme{seahorse} % or your preferred color  
theme
```

Please note that **Gotham** may not use all the colors defined in your favourite Beamer color theme. In particular, **Gotham** does not set a background color for the title; this will cause issues when using color themes like `whale` which set a white foreground for the title.

5.3 Notes on second screen

If you use the `[show notes on second screen]` option built into Beamer and compile with XeLaTeX, text on slides following the first section slide may be rendered in white instead of the regular color. This is due to a bug in Beamer or XeLaTeX itself. You can work around it either by compiling with LuaTeX or by adding the following code to your preamble to reset the text color on each slide.

```

\makeatletter
\def\beamer@framenotesbegin{\% at beginning of slide
  \usebeamercolor[fg]{normal text}
  \gdef\beamer@noteitems{\%}
  \gdef\beamer@notes{\%}
}
\makeatother

```

5.4 Standout frames with labels

Because the `standout` frame option creates a group to restrict the colour change to a single slide, labels defined after calling `standout` will stay local to the group. In other words, the following may result in a “label undefined” error.

```

\begin{frame}[standout, label=conclusion]{Conclusion}
  Awesome slide
\end{frame}

```

To fix this problem, change the order of the keys in the frame.

```

\begin{frame}[label=conclusion, standout]{Conclusion}
  Awesome slide
\end{frame}

```

This error can be unwittingly triggered if you export your slides from Emacs Org mode, which automatically adds labels after frame options. Alex Branham [offers](#) the following solution for Org mode users, using `org-set-property`.

```

* Start of a frame
:PROPERTIES:
:BEAMER_opt: label=conclusion,standout
:END:

```

5.5 Standout frames with Pandoc

With Pandoc versions prior 1.17.2 it was not possible to create standout frames because Pandoc only supported a specific list of frame attributes thus ignoring additional attributes such as `{.standout}`.

5.6 Other issues

- `enumitem` is not working with Beamer.

Todo

List of thing that could be improved (any volunteer welcome):

- Reduce the number of @ .
- Rename a lot of length with gotham at the beginning of their name.
- Turn internal length into `_dim`.
- Improve documentation.
- Add a hexagonal, wavy and add lengths on the blueprint layout backgrounds.
- Remove calc package (that can be replaced by xfp or just fp).
- Remove colors from tests inner and outer.
- Replace the `\setbeamertemplate{yy}[default/xx]` by `__gotham_inner_set_template:nn{tit` or merge them because the default values in dict/template are interesting but `__gotham_inner_set_template` are simpler.
- add colorset more blue-ish, green-ish ... from colorA etc.
- add Gotham to lists of Awesome Beamer themes.

6 License

Gotham is licensed under the terms of the [LaTeX project public license \(LPPL\) 1.3c](#) license.

7 Commands description for users

FONT

```
\iffontavailable \iffontavailable {\{list of fonts' names\}} {\{True code\}} {\{False code\}}
```

If all fonts in {\{list of fonts' names\}} are font then {\{True code\}} is executed else {\{False code\}}.

```
\usefonttheme{\usefonttheme[option1=value1, ...]{gotham}}
```

where the options are (default marked as `default: default`):

```
\titleformat = [{\default: textregular | lower | upper | titlecase}]  
\titleshape = [{\default: textregular | smallcaps | italic}]  
\subtitleformat = [{\default: textregular | lower | upper | titlecase}]  
\subtitleshape = [{\default: textregular | smallcaps | italic}]  
\frametitleformat = [{\default: textregular | lower | upper | titlecase}]  
\frametitleshape = [{\default: textregular | smallcaps | italic}]  
\framesubtitleformat = [{\default: textregular | lower | upper | titlecase}]  
\framesubtitleshape = [{\default: textregular | smallcaps | italic}]  
\partformat = [{\default: textregular | lower | upper | titlecase}]  
\partshape = [{\default: textregular | smallcaps | italic}]  
\sectionformat = [{\default: textregular | lower | upper | titlecase}]  
\sectionshape = [{\default: textregular | smallcaps | italic}]  
\subsectionformat = [{\default: textregular | lower | upper | titlecase}]  
\subsectionshape = [{\default: textregular | smallcaps | italic}]
```

The 'package' (`usefonttheme`) options can control both shape and format of title (of the presentation), subtitle, part title, section title, subsection title, frametitle and framesubtitle.

COLOR

```
\colorlet{colorPale}      \colorlet {\colorPale} {\gPaleYell}
set_gotham_palette_colors \colorlet {\colorDark} {\gDarkBlack}
\colorlet {\colorA} {\gAnthracite}
\colorlet {\colorAreversed} {\gLightTeal}
\colorlet {\colorB} {\gMidGrey}
\colorlet {\colorC} {\gDeepYellow}
\colorlet {\colorD} {\gLightOrange}
\colorlet {\colorE} {\gLightGreen}
```

Setup the colors use for presentations:

- `colorPale` is used for BG in light mode
- `colorDark` is used for FG in light mode
- `colorA` is used for frametitle and standout BG in light mode
- `colorAreversed` is used for frametitle and standout BG in dark mode
- `colorB` is used for progress bar and blocks BG
- `colorC` is used for progress bar FG
- `colorD` is used for alert FG/BG depending on the block mode
- `colorE` is used for example FG/BG depending on the block mode

```
\colorlet{colorBG}{colorPale} \colorlet {\colorBG} {\colorPale}
set_functional_colors      \colorlet {\colorFG} {\colorDark}
\colorlet {\colorFrametitle} {\colorA}
\colorlet {\colorStandout} {\colorA}
\colorlet {\colorStandin} {\colorA}
\colorlet {\colorTitlepage} {\colorA}
\colorlet {\colorFiligrane} {\colorB}
\colorlet {\colorBackElement} {\colorB}
\colorlet {\colorProgBar} {\colorC}
\colorlet {\colorAlert} {\colorD}
\colorlet {\colorExample} {\colorE}
```

Setup the default color aliases used in the presentation theme definitions. These aliases are partly redefined by dark/light/transparent modes.

`\usecolortheme` `\usecolortheme[<option1=value1, ...]<gotham>}`

where the options are (default marked as `default: default`):

`<background> = [<default: transparent / light / dark>]`
`<block> = [<default: native / fill / transparent>]`
`<colorset> = [<default: anthracite / red >]`

The 'package' (`usecolortheme`) options can control color mode (dark, ligh or transparent background) and the block (native or fill or transparent). Block environments such as `theorem` and `example` have no background color by default. The option `block=fill` sets a background color based on the background and foreground of `normal text`. The option `block=transparent` reverts the block environments to an empty background, which can be useful if changing colors mid-presentation. The option `colorset=red` changes the colorset used to define a color theme.

INNER

Titlepage

`\gothamtitlepagelogo` The command to insert the institute logo on title page. This command is left empty by default, to be redefined by users

`\gothamtitlepagebg` The command to insert the background title page This command is left empty by default, to be redefined by users

`__gotham_set_template:nn` `__gotham_set_template:nn {<element>} {<option>}`

Function that test if a beamertemplate with the given element and option name exists. If it exists then it is set (applied), otherwise an error is raised.

`\useinnertheme` `\useinnertheme[<option1=value1, ...]<gotham>}`

where the options are (default marked as `default: default`):

`<title page> = [<default: gotham normal / gotham splitvert / gotham dividedpic / gotham reversed>]`

The 'package' (`useinnertheme`) options can set different title page templates.

Backgrounds

\l__gotham_template_name_prop

Dictionary/map of template elements and predefined option according to the context.
Naming convention: template/What/Who, i.e. Name: key=background canvas/watermark, value = gotham draft

\defbeamertemplate{background}{name}{def} \defbeamertemplate {⟨background canvas⟩} {⟨chosen name⟩} {⟨definition⟩}

The `background` `canvas` and the `background` beamer templates can be redefined by users if wanted/needed. By default these templates are empty (except the color in background canvas when it not transparent).

\begin{frame}[noBGC] Add a frame option `noBGC` to display an empty background canvas.

\l_gotham_defaultWatermark

Boolean to triggering if watermark should be displayed by default (without giving the frame option). The variable is `false` by default.

\begin{frame}[watermark] Add a frame option `watermark` to display watermark in background.

\begin{frame}[nowatermark]

Add a frame option `nowatermark` to do not display nowatermark in background.

\useinnertheme \useinnertheme[⟨option1=value1, ...⟩]{⟨gotham⟩}
where the options are (default marked as `default: default`):
⟨watermark default⟩ = [⟨default: off / on ⟩]
⟨watermark template⟩ = [⟨default: gotham draft / ...⟩]

The 'package' (`useinnertheme`) options can control `background` (and `background canvas`) templates according to situations. Block environments such as `theorem` and `example` have no background color by default. The option `watermark default=on` can enable the `watermark template` on every frame; but it can still be turned off for specific frames when using the frame option `nowatermark`.

Stand IN/OUT

\begin{frame}[c] Add a frame option `c` for enhanced vertically centered text in the frame.

`\begin{frame}[standout]` Add a frame option **standout** to display the standout frame template.

`\begin{frame}[standin]` Add a frame option **standin** to display the standin frame template.

```
\useinnertheme \useinnertheme[<option1=value1, ...>]{gotham}
```

where the options are (default marked as `default`):
`(standin template) = [<default: gotham / ...>]`
`(standout template) = [<default: gotham / ...>]`
`(standin BG template) = [<default: gotham / ...>]`
`(standout BG template) = [<default: gotham / ...>]`

The 'package' (`useinnertheme`) options can control **standout** (and **standin**) templates. These templates are activated when giving the frame option `\begin{frame}[standin]` and **standout**.

Sections

`\begin{frame}[part]` Add a frame option **part** to display the part frame template.

`\begin{frame}[section]` Add a frame option **section** to display the section frame template.

`\begin{frame}[subsection]` Add a frame option **subsection** to display the subsection frame template.

`\begin{frame}[subsubsection]` Add a frame option **subsubsection** to display the subsubsection frame template.

`\partContentName` Commands containing the 'table of contents' title for part, section and subsection (if theses ToC frames are enabled). An option for subsubsection is not useful (at least up to understanding of the moment) because we do not display frame with the content of a subsubsection since it is the small unity we are working with.

`\gothamProgressSectionHeight` Variables used to defined the progress bar in section pages. If the vertical size of the bar want to be changed, the command `\setlength{\gothamProgressSectionHeight}{<0.4pt>}` can be used.

`\sectionhoffset` length controlling the horizontal offset of the (section title + progress bar) block. Can be useful when extra stuff want to be display on sides of the block. The default value is 0.

`\useinnertheme \useinnertheme[<option1=value1, ...>]{gotham}`

where the options are (default marked as `default: default`):

```
<partframe template> = [<default: gotham progressbar | gotham simple | gotham splitvert progressbar | gotham splitvert simple | gotham progressvert | ...>]
<partframe default> = [<default: on | off>]
<sectionframe template> = [<default: gotham progressbar | gotham simple | gotham splitvert progressbar | gotham splitvert simple | gotham progressvert | ...>]
<sectionframe default> = [<default: on | off>]
<subsectionframe template> = [<default: gotham progressbar | gotham simple | gotham splitvert progressbar | gotham splitvert simple | gotham progressvert | ...>]
<subsectionframe default> = [<default: on | off>]
<subsubframe template> = [<default: gotham progressbar | gotham simple | gotham splitvert progressbar | gotham splitvert simple | gotham progressvert | ...>]
<subsubframe default> = [<default: on | off>]
```

The 'package' (`useinnertheme`) options can control `partframe` templates (or `sectionframe`, `subsectionframe` and `subsubsectionframe` respectively), which define the style of the partframe (or `sectionframe`, `subsectionframe` and `subsubsectionframe` respectively) displayed at every new beginning of sectioning. These templates can be disabled (or re-enabled) by default using the option `partframe default` (or `sectionframe`, `subsectionframe` and `subsubsectionframe` respectively).

Table of Content

`\begin{frame}[toc]` Add a frame option `toc` to display the toc frame template.

`\begin{frame}[tocpart]` Add a frame option `tocpart` to display the tocpart frame template.

`\begin{frame}[tocsec]` Add a frame option `tocsec` to display the tocsec frame template.

`\begin{frame}[tocsubsec]` Add a frame option `tocsubsec` to display the tocsubsec frame template.

```
\begin{frame}[tocsubsubsec]
```

Add a frame option `tocsubsubsec` to display the `tocsubsubsec` frame template.

```
\useinnertheme \useinnertheme[<option1=value1, ...]>{\gotham}
```

where the options are (default marked as `default: default`):

```
<tocframe template> = [<default: gotham bullet / gotham simple / ...>]
<parttocframe template default> = [<default: gotham simple / gotham bullet>]
<parttocframe default> = [<default: on / off>]
<sectocframe template default> = [<default: gotham simple / gotham bullet>]
<sectocframe default> = [<default: on / off>]
<subsectocframe template default> = [<default: gotham simple / gotham bullet>]
<subsectocframe default> = [<default: on / off>]
```

The 'package' (`useinnertheme`) options can control `parttocframe templates` (or `sectocframe` and `subsectocframe` respectively), which define the style of the table of content for `partframe` (or `sectionframe`, and `subsectionframe` respectively) displayed at every new beginning of sectioning. These templates can be disabled (or re-enabled) by default using the option `parttocframe default` (or `sectocframe` and `subsectocframe` respectively).

Environments styles

```
\begin{block}
```

Three boxed environment are defined by default: `block`, `alertblock` and `exampleblock`.

```
\begin{alertblock}
```

The style of blocks can be changed using `\setbeamertemplate{blocks}[rounded][shadow=true]`.

```
\begin{exampleblock}
```

```
\begin{itemize}
```

Three level of itemize environment are defined by default with decreasing size: `circle`, `triangle` and `square`.

```
\defbeamertemplate{caption}
```

```
\defbeamertemplate{footnote}
```

Gotham defines float captions with a numbered style and footnotes with traditional style (color can be tuned with `\setbeamercolor{footnote}`).

OUTER

\l__gotham_template_name_prop

Dictionary/map of template elements and predefined option according to the context.
Naming convention: template/What/Who, i.e. Name: key=background canvas/watermark, value = gotham draft

__gotham_set_template:nn __gotham_set_template:nn {<element>} {<option>}

Function that test if a beamertemplate with the given element and option name exists.
If it exists then it is set (applied), otherwise an error is raised.

Sidebars

\sidebarRightHOffset Length controling the horizontal offset in order to position `\gothamRightFiligrane`
\sidebarLeftHOffset (respectively `\gothamLeftFiligrane`) when using the default sidebar canvas (right and left) from gotham.

\gothamRightFiligrane Commands used internally by `\setbeamertemplate{sidebar~canvas~right}[default/gotham-filigrane]`
\gothamLeftFiligrane (left respectively), that are empty by default. But these commands can be simply redefined to custom watermarks (filigrane) in sidebars.

\l_gotham_defaultEdging Boolean to triggering if edging should be displayed by default (without giving the frame option). The variable is `false` by default.

\begin{frame}[edging] Add a frame option `edging` to display edging in sidebar canvas.

\begin{frame}[noedging] Add a frame option `noedging` to do not display noedging in sidebar canvas.

```
\useoutertheme{gotham}
```

where the options are (default marked as `default`):

```
(edging default) = [⟨default: off / on⟩]
⟨sidebar canvas left template⟩ = [⟨default: gotham / ...⟩]
⟨sidebar canvas right template⟩ = [⟨default: gotham filigrane / empty / ...⟩]
```

The 'package' (`useoutertheme`) options can control `sidebar canvas right` (and `sidebar canvas left`) templates. These templates are activated when giving the frame option `\begin{frame}[edging]`. The option `edging default=on` can enable the `sidebar canvas right` (and `sidebar canvas left`) templates on every frame; but it can still be turned off for specific frames when using the frame option `noedging`.

Navigation & Logo

```
\defbeamertemplate{navigation-symbols}{empty}
```

By default the navigation symbols are disable.

```
\defbeamertemplate{navigation-symbols}{default}
```

Navigation symbols can be turned on using `\setbeamertemplate{navigation symbols}[default]`.

```
\begin{frame}[nologo]
```

Add a frame option `nologo`, if you do not want your logo to be displayed.

Headline & Frametitle

Headline

Frametitle

```
\gothamFrametitleToppadding
\gothamFrametitleBottompadding
\gothamFrametitleLeftpadding
\gothamFrametitleRightpadding
```

Dimensions controlling the top, bottom, left and right padding in the frametitle.

```
\gothamInstituteLogoSquare[height] \height [⟨height of the logo use in inclugraphics (4ex by default)⟩]
```

Command to set the image logo to include.

```
\gothamFrameSubtitleSep
```

Command that can be redefined to control the separator between the title of the frame and its subtitle. For example if a default Beamer style is desired, one can use `\renewcommand{\gothamFrameSubtitleSep}{\text{--}}`. By default it is a hyphen.

```
\gothamFramesubtitleStrutend
```

Variable vertical length used to adapte the bottom padding when a subtitle is given.

```
\useoutertheme \useoutertheme[<option1=value1, ...]>{\gotham}
```

where the options are (default marked as `default: default`):

```
<frametitle template> = [<default: gotham subsameline | gotham subnewline | ... >]
```

```
<framesubtitle template> = [<default: gotham subnewline | ... >]
```

The 'package' (`useoutertheme`) options can control `frametitle` (and `framesubtitle`) templates.

Continuation

```
\useoutertheme \useoutertheme[<option1=value1, ...]>{\gotham}
```

where the options are (default marked as `default: default`):

```
<frametitle continuation template> = [<default: gotham | tot | beamer | ... >]
```

The 'package' (`useoutertheme`) options can control `frametitle continuation` templates.

Footer & Footline

Footline

```
\begin{frame}[nofootline]
```

Add a frame option `nofootline` to do not display nofootline.

```
\gothamFootlineVOffset  
\gothamFootlineHRightOffset  
\gothamFootlineHeight  
\gothamFootlineDepth
```

Lengths controlling the position of `footline`. `\gothamFootlineVOffset` is controlling vertical space between to bottom of the text (or the footnote) and the footline. `\gothamFootlineVOffset` is by default -0.5ex, to have more space in the frame but if the footer is not really used, the space can be even more optimized using `\setlength{\gothamFootlineVOffset}{-2.0ex}`. `\gothamFootlineHRightOffset` is horizontal space between the right corner and the footline. Obviously, it can be back to `normal` setting it to 0pt. `\gothamFootlineHeight` and `\gothamFootlineDepth` are controlling the height of the footline and the position of the text within.

Footer

`\gothamLeftFooterPadding` Lengths controlling the position of footer. `\gothamFooterHOffset` is controlling the horizontal space between the footer and the bottom of the page (or the progressbar).
`\gothamRightFooterPadding` `\gothamFooterHOffset` and `\gothamLeftFooterPadding` are controlling the space between the left and right side of the footer and the border of the page.

`\begin{frame}[nofooter]` Add a frame option `nofooter` to do not display nofooter.

`\l_gotham_defaultRotateFooter`

Boolean to triggering if rotated footer should be displayed by default (without giving the frame option). The variable is `false` by default.

`\begin{frame}[rotateFooter]`

Add a frame option `rotateFooter` to display rotated footer.

`\begin{frame}[noRotateFooter]`

Add a frame option `noRotateFooter` to display a none-RotateFooter.

`\useoutertheme \useoutertheme[<option1=value1, ...]<gotham>}`
where the options are (default marked as `default: default`):
`<rotateFooter default> = [<default: off / on >]`

The option `rotateFooter default=on` can enable the rotation of the footer on every frame; but it can all be turned on for specific frames when using the frame option `\begin{frame}[rotateFooter]`.

```
\gothamFootlineRuleLeftPadding
\gothamFootlineRuleHeight
\gothamFootlineRuleLength
\gothamHposLeftRotFooter
\gothamHposRightRotFooter
\gothamVposLeftRotFooter
\gothamVposRightRotFooter
```

Lengths controlling the position of footer. `\gothamFootlineRuleLeftPadding` is controlling the horizontal space between the left border of the page and the left side of the rule. `\gothamFootlineRuleHeight` is controlling the height of the rule use to delimit the footer. `\gothamFootlineRuleLength` is controlling the length of the rule use to delimit the footer. `\gothamHposLeftRotFooter` is controlling the horizontal positioning of the left part of the rotatated footer. `\gothamHposRightRotFooter` is controlling the horizontal positioning of the right part of the rotatated footer. `\gothamVposLeftRotFooter` is controlling the vertical positioning of the left part of the rotatated footer. `\gothamVposRightRotFooter` is controlling the vertical positioning of the right part of the rotatated footer.

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{<gotham>}
```

where the options are (default marked as `default: default`):

```
<footer template> = [<default: gotham / ... >]
```

The option `footer template` can which template to use as a footer.

Numbering

```
\gothamCircleNumberingVshift
\gothamCircleNumberingHshift
```

Variable lengths controling the vertical and horizontal positioning of the `circle` frame numbering template.

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{<gotham>}
```

where the options are (default marked as `default: default`):

```
<numbering> = [<default: none / framenumber / totalframenumber /
appendixframenumber / pagenumber / totalpagenumber / circle / ... >]
<framesubtitle template> = [<default: gotham subnewline / ...>]
```

The 'package' (`useoutertheme`) options can control `frame numbering` templates used in `footer` template.

MiniFrames & Progress bar

MiniFrames

Select the bullets shape

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{gotham}
```

where the options are (default marked as `default: default`):

```
<mini frames shape> = [<default: gotham minibullet / default (bullet from beamer) / tick / box / gotham box / gotham minibox / ... >]
```

```
<framesubtitle template> = [<default: gotham subnewline / ...>]
```

The 'package' (`useoutertheme`) options can control `frame numbering` templates used in `footer` template.

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{gotham}
```

where the options are (default marked as `default: default`):

```
<mini frames bundle> = [<default: gotham minibullet / default (bullet from beamer) / tick / box / gotham box / gotham minibox / ... >]
```

```
<framesubtitle template> = [<default: gotham subnewline / ...>]
```

The 'package' (`useoutertheme`) options can control `mini frame` templates.

MiniFrames Navigation

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{gotham}
```

where the options are (default marked as `default: default`):

```
<mini frames compress> = [<default: on / off >]
```

The 'package' (`useoutertheme`) options can control `compress` option in mini frames.

```
gothamZeroSectionframes
```

Boolean variable to flag if they are frame in a zeroth section. This variable helps to adapt the spreading of `mini frames nav` bar. This variable is automatically set if the spread is set correctly at the beginning of the presentation. If the spreading or the mini frame nav is disable at the zeroth section then reactivated latter, it might create unwanted spreading. In such situation the variable has to be set manually to correct the spreading.

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{gotham}
```

where the options are (default marked as `default: default`):

```
<mini frames nav spreading> = [<default: centering / spreading / left / right >]
```

The 'package' (`useoutertheme`) options can control spreading of the mini frames navigation.

```
\useoutertheme \useoutertheme[<option1=value1, ...>]{gotham}
```

where the options are (default marked as `default: default`):

```
<mini frames nav sectioning> = [<default: on / off >]
```

The 'package' (`useoutertheme`) options can control navigation sectioning option in mini frames.

`\useoutertheme \useoutertheme[<option1=value1, ...]<(gotham)>`
where the options are (default marked as `default`):
`<mini frames nav position> = [<default: none / head / foot / left / right>]`
The 'package' (`useoutertheme`) options can control navigation position option in mini frames.

Progress bar

`\gothamProgressHeadFootLineheight`

Variable vertical length defining the height of the progressbar.

`\l_gotham_ProgCircleMoving_bool`
`\l_gotham_progbar_advancement_tlbr_bool`
`\l_gotham_pmf_fn_bool`

Boolean variables controlling the direction of progression and if the current frame number is moving with the progression.

`\gothamProgressCircHeight`
`\gothamCounterCircleRadius`
`\gothamProgressCircBorderWidth`

Lengths controlling the aspect of `progress circle`. `\gothamProgressCircHeight` is controlling the inner height of the circle (related to its diameter). `\gothamCounterCircleRadius` is controlling the size of the counter circle containing the frame number. `\gothamProgressCircBorderWidth` is controlling width of the progress circle.

`\gothamInstituteLogoCircle[#1] \gothamInstituteLogoCircle [<height (4ex)>]`

Command that have to be redefined in order to include your circular logo. For example your can do `\renewcommand{\gothamInstituteLogoCircle}{\includegraphics[height=4ex]}`

`\useoutertheme \useoutertheme[<option1=value1, ...]<(gotham)>`
where the options are (default marked as `default`):
`<progressbar position> = [<default: foot / none / head / circlehead / ... >]`
The 'package' (`useoutertheme`) options can control `progress bar` templates that be placed in the head (over the frametitle), frametitle (under it), below the footer or the circlehead (around the logo in the frametitle).

`\useoutertheme \useoutertheme[option1=value1, ...]{gotham}`

where the options are (default marked as `default: default`):

`\progressbar style` = [`default: rectangle / rounded box / moving circle / fixed circle`]

The 'package' (`useoutertheme`) options can control `progress bar` style templates that

.

`\useoutertheme \useoutertheme[option1=value1, ...]{gotham}`

where the options are (default marked as `default: default`):

`\progressbar advancement` = [`default: tlbr / brlt`]

The 'package' (`useoutertheme`) options can control `progress bar` advancement: `tlbr` from top left corner to the bottom and right or `brlt` from the bottom right to the left and top.

`\useoutertheme \useoutertheme[option1=value1, ...]{gotham}`

where the options are (default marked as `default: default`):

`\progressbar mfn` = [`default: off / on`]

The 'package' (`useoutertheme`) options can control if the progress bar includes a miniframe navigation.

Most options are passed off to the component sub-packages.

8 Package implementation for developers

```
1  <*font>
2  \ProvidesExplPackage{beamerfontthemegotham}{2024-11-11}{1.2.0.a}{gotham font theme}
3  \RequirePackage{expl3}
4  \RequirePackage{xparse}
5  \RequirePackage{etoolbox}
6  \RequirePackage{ifxetex}
7  \RequirePackage{ifluatex}
```

FONT

`font_messages` Definition of the messages that are used and reused by font theme.

```
8  \msg_new:nnn { gotham } { font-not-found }
9  {
10    Could-not-find-font-'#1'.\c_space_tl
11 }
12
13 \msg_new:nnn { gotham } { fonts-not-available }
14 {
15   No-suitable-fonts-found.~Using-fallback-fonts.
16 }
17
18 \msg_new:nnn { gotham } { compiler-xe-or-lua }
19 {
20   You-need-to-compile-with-XeLaTeX-or-LuaLaTeX-to-use-the-Fira-fonts.
21 }
```

(End of definition for `font messages`. This variable is documented on page ??.)

`\g_gotham_fontsnotfound_int:n` Counter for the number of font not found.

```
22 \int_new:N \g_gotham_fontsnotfound_int
```

(End of definition for `\g_gotham_fontsnotfound_int:n`. This variable is documented on page ??.)

\checkfont:n #1 : Name of the font.

Command to check if one font exist.

The following test files are used for this code: gotham-test-035.

```
23 \cs_new_protected:Nn \checkfont:n
24 {
25   \fontspec_font_if_exist:nF { #1 }
26   {
27     % false: check with regular postfix.
28     \fontspec_font_if_exist:nF { #1-Regular }
29   {
30     % false: raise a warning and increment the number of font not found.
31     \int_incr:N \g_gotham_fontsnotfound_int
32     \msg_warning:nnn { gotham } { font-not-found } { #1 }
33   }
34 }
35 }
```

\iffontavailable Command to check if a list of font is available.

The following test files are used for this code: gotham-test-035.

```
36 \providetcommand{\iffontavailable}[3]
37 {
38   \int_zero:N \g_gotham_fontsnotfound_int
39   \clist_map_function:nN { #1 } \checkfont:n
40   \int_compare:nTF { \g_gotham_fontsnotfound_int = 0 }
41   {%
42     #2
43   }{%
44     #3
45   }
46 }
```

Load_if_fonts_available If fontspec is loadable (ie. if xelatex or lualatex), then load available fonts, otherwise raise a warning and go on.

The following test files are used for this code: gotham-test-035.

```
47 \ifboolexpr{bool~{xetex}~or~bool~{luatex}}{
48   % if fontspec loaded pass option otherwise load fontspec.
```

```

49  \@ifpackageloaded{fontspec}{
50    \PassOptionsToPackage{no-math}{fontspec}
51  }{
52    \RequirePackage[no-math]{fontspec}
53  }
54 %
55 % We search for regular, italic, light, light italic, fonts under the default |Fira Sans| names.
56 \iffontsavailable{FiraSans-Light.otf,
57   FiraSans-LightItalic.otf,
58   FiraSans-Regular.otf,
59   FiraSans-Italic.otf}
60 {
61   \setsansfont[ItalicFont={FiraSans-LightItalic.otf},
62   BoldFont={FiraSans-Regular.otf},
63   BoldItalicFont={FiraSans-Italic.otf}]
64   {FiraSans-Light.otf}
65 }{
66 % If this fails, the suffix OT --- used by some Linux distributions --- will be tried.
67 \iffontsavailable{FiraSans-Light-OT,
68   FiraSans-LightItalic-OT,
69   FiraSans-Regular-OT,
70   FiraSans-Italic-OT}
71 {
72   \setsansfont[ItalicFont={Fira-Sans-LightItalic-OT},
73   BoldFont={Fira-Sans-Regular-OT},
74   BoldItalicFont={Fira-Sans-Italic-OT}]
75   {Fira-Sans-Light-OT}
76 }{
77 % If this also fails, a warning will be displayed and the standard fonts will be used.
78 \msg_warning:nn { gotham } { fonts-not-available }%
79 }
80 }
81 %
82 % We search for regular, mono, and mono bold fonts under the default |Fira Mono| names.
83 \iffontsavailable{FiraMono-Medium.otf, FiraMono-Bold.otf}{
84   \setmonofont[BoldFont={FiraMono-Medium.otf}]{FiraMono-Bold.otf}
85 }{
86 % If this fails, the suffix OT --- used by some Linux distributions --- will be tried.
87 \iffontsavailable{Fira-Mono-Medium-OT, Fira-Mono-Bold-OT}{
88   \setmonofont[BoldFont={Fira-Mono-Medium-OT}]{Fira-Mono-Bold-OT}
89 }{
90 % If this also fails, a warning will be displayed and the standard fonts will be used.
91 \msg_warning:nn { gotham } { fonts-not-available }

```

```

92    }
93  }
94 %
95 % Add a feature for numbers in tables.
96 \AtBeginEnvironment{tabular}{
97   \addfontfeature{Numbers={Monospaced}}
98 }
99 }{
100 % If compiled with pdf\LaTeX{}, then apply a dirty patch (that will not do the job but supp
101 \msg_warning:nn { gotham } { compiler-xe-or-lua }
102 \DeclareFontShape{OT1}{cmss}{bx}{sc}{<-> cmbcsc10}{}
103 \DeclareFontShape{OT1}{cmss}{bx}{it}{<->sub*cmss/m/sl}{}
104 }

```

(End of definition for *Load fonts if available*. This function is documented on page ??.)

`\setbeamerfont{title}` Set all needed font environment variables:shape, size, series. Remark: Case is missing.
`general_font_definitions` The following test files are used for this code: *gotham-test-035*, *gotham-test-036*.

```

105 \setbeamerfont{title}{size=\Large, series=\bfseries}
106 \setbeamerfont*{subtitle}{size=\large}
107 \setbeamerfont{author}{size=\small}
108 \setbeamerfont{date}{size=\small}
109
110 \setbeamerfont{section~title}{size=\Large, series=\bfseries}
111 \setbeamerfont{subsection~title}{size=\large, series=\bfseries}
112 \setbeamerfont{subsubsection~title}{size=\normalsize, series=\bfseries}
113
114 \setbeamerfont{frametitle}{size=\large, series=\bfseries}
115 \setbeamerfont{frametitleToc}{size=\LARGE, series=\bfseries}
116 \setbeamerfont{frametitleSection}{size*={60}{1}, series=\bfseries}
117
118 \setbeamerfont{page~number~in~head/foot}{size=\footnotesize}
119 \setbeamerfont{footline}{size=\scriptsize}
120
121 \setbeamerfont{block~title}{size=\normalsize, series=\bfseries}
122 \setbeamerfont{block~title~alerted}{size=\normalsize, series=\bfseries}
123 \setbeamerfont{caption}{size=\small}
124 \setbeamerfont{caption~name}{series=\bfseries}
125 \setbeamerfont{description~item}{series=\bfseries}
126
127 \setbeamerfont{bibliography~entry~author}{size=\normalsize, series=\normalfont}
128 \setbeamerfont{bibliography~entry~title}{size=\normalsize, series=\bfseries}
129 \setbeamerfont{bibliography~entry~location}{size=\normalsize, series=\normalfont}

```

```

130 \setbeamerfont{bibliography~entry~note}{size=\small, series=\normalfont}
131 \setbeamerfont{standout}{size=\Large, series=\bfseries}
```

(End of definition for `\setbeamerfont{title}` and general font definitions. These functions are documented on page ??.)

`__gotham_title_format:n` Pre-hooks that will be inserted to control case format of titles in addition with the fonts set.

The following test files are used for this code: `gotham-test-035`, `gotham-test-036`.

```

132 \def\gotham@titleformat#1{#1}
133 \def\gotham@subtitleformat#1{#1}
134 \def\gotham@parttitleformat#1{#1}
135 \def\gotham@sectiontitleformat#1{#1}
136 \def\gotham@subsectiontitleformat#1{#1}
137 \def\gotham@frametitleformat#1{#1}
138 \def\gotham@framesubtitleformat#1{#1}
139 % IF ONE DAY: I can patch beamer with expl3, I will use the following commands instead.
140 % %\cs_new:Npn \__gotham_unchanged:n #1 {#1}
141 % %\cs_new:Npn \__gotham_title_format:n #1 {#1}
142 % %\cs_new:Npn \__gotham_subtitle_format:n #1 {#1}
143 % %\cs_new:Npn \__gotham_part_title_format:n #1 {#1}
144 % %\cs_new:Npn \__gotham_section_title_format:n #1 {#1}
145 % %\cs_new:Npn \__gotham_subsection_title_format:n #1 {#1}
146 % %\cs_new:Npn \__gotham_frametitle_format:n #1 {#1}
147 % %\cs_new:Npn \__gotham_framesubtitle_format:n #1 {#1}
```

`\beamer@title` Since, case feature is not available in `setbeamerfont`; to make the uppercase, lowercase

`\beamer@subtitle` and title-case macros work in the title, subtitle, etc., we have to patch the appropriate

`\sectionentry` `beamer` commands that set their values. This solution was suggested by Enrico Gregorio

in an answer to [this StackExchange question](#). Remark: `patchcmd` from `etoolbox` (or other), is not compatible with `expl3`.

The following test files are used for this code: `gotham-test-035`, `gotham-test-036`.

```

148 \ExplSyntaxOff
149 \patchcmd{\beamer@title}
150   {\def\inserttitle{#2}}
151   {\def\inserttitle{\gotham@titleformat{#2}}}
152   % {\def\inserttitle{ \__gotham_title_format:n{#2} }}
153   {}
154 {\PackageError{beamerfontthemegotham}{Patching~title~failed}\@ehc}
```

```

155 \patchcmd{\beamer@subtitle}
156   {\def\insertsubtitle{#2}}
157   {\def\insertsubtitle{{\gotham@subtitleformat{#2}}}}
158   % {\def\insertsubtitle{ \__gotham_subtitle_format:n{#2} }}
159   {}
160   {\PackageError{beamerfontthemegotham}{Patching~subtitle~failed}\@ehc}
161 \patchcmd{\sectionentry} % beamerbasenavigation.sty 1.335
162   {\def\insertsectionhead{#2}}
163   {\def\insertsectionhead{\gotham@sectiontitleformat{#2}}}
164   {}
165   {\PackageError{beamerfontthemegotham}{Patching~section~title~failed}\@ehc}%
166 %
167 %% NOT WORKING YET!
168 %% \patchcmd{\subsectionentry} % beamerbasenavigation.sty 1.384
169 %%   {\def\insertsubsectionhead{##5}}
170 %%   {\def\insertsubsectionhead{\gotham@subsectiontitleformat{##5}}}
171 %%   {}
172 %%   {\PackageError{beamerfontthemegotham}{Patching~subsection~title~failed}\@ehc}%
173 %
174 \tempswafalse
175 \patchcmd{\beamer@section} % beamerbasesection.sty 1. 209
176   {\def\insertsectionhead{\hyperlink{Navigation\the\c@page}{#1}}}
177   {\def\insertsectionhead{\hyperlink{Navigation\the\c@page}{\gotham@sectiontitleformat{#1}}}}
178   % \__gotham_section_title_format:n{#2}
179   {\@tempswatrue}
180   {}
181 \patchcmd{\beamer@section} % beamerbasesection.sty 1. 209
182   {\edef\insertsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{\unexpanded{#1}}}}
183   {\edef\insertsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{\noexpand\gotham@sectiontitleformat{#1}}}}
184   % \exp_not:N \__gotham_section_title_format:n {#1}
185   {\@tempswatrue}
186   {}
187 \if@tempswa\else
188   {\PackageError{beamerfontthemegotham}{Patching~section~title~failed}\@ehc}
189 \fi
190 \tempswafalse
191 %
192 %% NOT WORKING YET !
193 %% \patchcmd{\beamer@subsection} % beamerbasesection.sty 1. 209
194 %%   {\def\insertsubsectionhead{\hyperlink{Navigation\the\c@page}{#1}}}
195 %%   {\def\insertsubsectionhead{\hyperlink{Navigation\the\c@page}{\gotham@subsectiontitleformat{#1}}}}
196 %%   % \__gotham_subsection_title_format:n{#2}
197 %%   {\@tempswatrue}

```

```

198 %%  {}
199 %% \patchcmd{\beamer@subsection} % beamerbasesection.sty 1. 209
200 %% {\protected@edef\insertsubsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{\#1}}}
201 %% {\protected@edef\insertsubsectionhead{\noexpand\hyperlink{Navigation\the\c@page}{\noexpa
202 %% % \exp_not:N \__gotham_subsection_title_format:n {\#1}}
203 %% {\@tempswatru
204 %% {}}
205 %% \if@tempswa\else
206 %% {\PackageError{beamerfontthemegotham}{Patching~subsection~title~failed}\@ehc}
207 %% \fi%
208 %% \@tempswafalse
209 %
210 %
211 % Similarly, to make the |\MakeLowercase| and |\MakeUppercase| macros work in the frame titl
212 \providecommand{\beamer@insertframetitlecontinuation}{%
213   \usebeamertemplate*{frametitle~continuation}
214 }
215 \patchcmd{\beamer@@frametitle} % beamerbaselocalstructure.sty 1. 32
216   {\gdef\insertframetitle{\%
217     #2%
218     \ifnum\beamer@autobreakcount>0
219       \relax{}\space%
220       \beamer@insertframetitlecontinuation%
221     \fi%
222   }}%
223 }
224 {\gdef\insertframetitle{\%
225   \gotham@frametitleformat{\#2}%
226   % \__gotham_frametitle_format:n {\#2}
227   \ifnum\beamer@autobreakcount>0
228     \relax{}\space%
229     \beamer@insertframetitlecontinuation%
230   \fi%
231 }}%
232 }
233 {}
234 {\PackageWarning{beamerfontthemegotham}{Patching~frametitle~failed}\@ehc}
235 %
236 %% NOT WORKING YET !
237 %% \patchcmd{\framesubtitle} % beamerbaselocalstructure.sty 1.55
238 %% {\only#2{\ifblank{\#1}{}{\gdef\insertframesubtitle{\#1}\beamer@aftersubtitle}}}
239 %% {\only{\#2}{\ifblank{\#1}{}{\gdef\insertframesubtitle{\#1}\beamer@aftersubtitle}}}
240 %% {}

```

```

241 %% {\PackageWarning{beamerfontthemegotham}{Patching~framesubtitle~failed}\@ehc}
242 %
243 \ExplSyntaxOn

```

(End of definition for \beamer@title, \beamer@subtitle, and \sectionentry. These functions are documented on page ??.)

font_key_interface Controls the format and shape of the title (of the presentation), subtitle, part title, section title, subsection title, frametitle and framesubtitle.

The following test files are used for this code: gotham-test-035, gotham-test-036.

```

244 \keys_define:nn { gotham / font }
245 {
246   % format title
247   format-title .choice:,
248   format-title .usage:n = { general },
249   format-title .default:n = { regular },
250   format-title / regular .code:n =
251   {
252     \let\gotham@titleformat\@empty
253     % \cs_set_eq:NN \__gotham_title_format:n \__gotham_unchanged:n
254   },
255   format-title / lower .code:n =
256   {
257     \let\gotham@titleformat \text_lowercase:n \%lowercase
258     % \cs_set_eq:NN \__gotham_title_format:n \text_lowercase:n
259     \PackageWarning{ gotham } { Be~aware~that~format~title=lower~can~lead~to~problems. }
260   },
261   format-title / upper .code:n =
262   {
263     \let\gotham@titleformat \text_uppercase:n \%uppercase
264     % \cs_set_eq:NN \__gotham_title_format:n \text_uppercase:n
265     \PackageWarning{ gotham } { Be~aware~that~format~title=upper~can~lead~to~problems. }
266   },
267   format-title / titlecase .code:n =
268   {
269     \let\gotham@titleformat \text_titlecase_all:n \%MakeTitlecase
270     % \cs_set_eq:NN \__gotham_title_format:n \text_titlecase_all:n
271     \PackageWarning{ gotham } { Be~aware~that~format~title=titlecase~can~lead~to~problems. }
272   },
273   format-title / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_value_tl
274 }
275 \keys_define:nn { gotham / font }
276 {

```

```

277 % shape title
278 shape~title .choice:,,
279 shape~title .usage:n = { general },
280 shape~title .default:n = { regular },
281 shape~title / regular .code:n =
282 {
283   \setbeamerfont{title}{shape=\normalfont}
284 },
285 shape~title / smallcaps .code:n =
286 {
287   \setbeamerfont{title}{shape=\scshape}
288 },
289 shape~title / italic .code:n =
290 {
291   \setbeamerfont{title}{shape=\itshape}
292 },
293 shape~title / unknown .code:n = { \PackageWarning{ gotham } { The~choice~' \l_keys_value_tl' }
294 }

295 \keys_define:nn { gotham / font }
296 {
297
298 % format subtitle
299 format~subtitle .choice:,,
300 format~subtitle .usage:n = { general },
301 format~subtitle .default:n = { regular },
302 format~subtitle / regular .code:n =
303 {
304   \let\gotham@subtitleformat\empty
305   % \cs_set_eq:NN \__gotham_subtitle_format:n \__gotham_unchanged:n
306 },
307 format~subtitle / lower .code:n =
308 {
309   \let\gotham@subtitleformat \text_lowercase:n \%lowercase
310   % \cs_set_eq:NN \__gotham_subtitle_format:n \text_lowercase:n
311   \PackageWarning{ gotham } { Be~aware~that~format~subtitle=lower~can~lead~to~problems. }
312 },
313 format~subtitle / upper .code:n =
314 {
315   \let\gotham@subtitleformat \text_uppercase:n \%uppercase
316   \cs_set_eq:NN \__gotham_subtitle_format:n \text_uppercase:n
317   \PackageWarning{ gotham } { Be~aware~that~format~subtitle=upper~can~lead~to~problems. }
318 },
319 format~subtitle / titlecase .code:n =

```

```

320  {
321   \let\gotham@subtitleformat \text_titlecase_all:n \%MakeTitlecase
322   % \cs_set_eq:NN \__gotham_subtitle_format:n \text_titlecase_all:n \%MakeTitlecase
323   \PackageWarning{ gotham } { Be~aware~that~format~subtitle=titlecase~can~lead~to~problems.
324 },
325   format~subtitle / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_value_
326 }
327 \keys_define:nn { gotham / font }
328 {
329   % shape subtitle
330   shape~subtitle .choice:,
331   shape~subtitle .usage:n = { general },
332   shape~subtitle .default:n = { regular },
333   shape~subtitle / regular .code:n =
334 {
335   \setbeamerfont{subtitle}{shape=\normalfont}
336 },
337   shape~subtitle / smallcaps .code:n =
338 {
339   \setbeamerfont{subtitle}{shape=\scshape}
340 },
341   shape~subtitle / italic .code:n =
342 {
343   \setbeamerfont{subtitle}{shape=\itshape}
344 },
345   shape~subtitle / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_value_
346 }

347
348 \keys_define:nn { gotham / font }
349 {
350   % format frametitle
351   format-frametitle .choice:,
352   format-frametitle .usage:n = { general },
353   format-frametitle .default:n = { regular },
354   format-frametitle / regular .code:n =
355 {
356   \let\gotham@frametitleformat\empty
357   % \cs_set_eq:NN \__gotham_frametitle_format:n \__gotham_unchanged:n
358 },
359   format-frametitle / lower .code:n =
360 {
361   \let\gotham@frametitleformat \text_lowercase:n \%lowercase
362   % \cs_set_eq:NN \__gotham_frametitle_format:n \text_lowercase:n

```

```

363  \PackageWarning{ gotham } { Be~aware~that~format~frametitle=lower~can~lead~to~problems. }
364 },
365 format~frametitle / upper .code:n =
366 {
367   \let\gotham@frametitleformat \text_uppercase:n \%uppercase
368   \% \cs_set_eq:NN \__gotham_frametitle_format:n \text_uppercase:n
369   \PackageWarning{ gotham } { Be~aware~that~format~frametitle=upper~can~lead~to~problems. }
370 },
371 format~frametitle / titlecase .code:n =
372 {
373   \let\gotham@frametitleformat \text_titlecase_all:n \%Maketitlecase
374   \% \cs_set_eq:NN \__gotham_frametitle_format:n \text_titlecase_all:n \%MakeTitlecase
375   \PackageWarning{ gotham } { Be~aware~that~format~frametitle=titlecase~can~lead~to~problems. }
376 },
377 format~frametitle / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_val
378 }
379 \keys_define:nn { gotham / font }
380 {
381   % shape frametitle
382   shape~frametitle .choice:,
383   shape~frametitle .usage:n = { general },
384   shape~frametitle .default:n = { regular },
385   shape~frametitle / regular .code:n =
386 {
387     \setbeamerfont{frametitle}{shape=\normalfont}
388   },
389   shape~frametitle / smallcaps .code:n =
390 {
391     \setbeamerfont{frametitle}{shape=\scshape}
392   },
393   shape~frametitle / italic .code:n =
394 {
395     \setbeamerfont{frametitle}{shape=\itshape}
396   },
397   shape~frametitle / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_val
398 }
399 \keys_define:nn { gotham / font }
400 {
401   % format framesubtitle
402   format~framesubtitle .choice:,
403   format~framesubtitle .usage:n = { general },
404   format~framesubtitle .default:n = { regular },

```

```

406   format-framesthumbnail / regular .code:n =
407   {
408     \let\gotham@framesthumbnailformat\empty
409     % \cs_set_eq:NN \__gotham_framesthumbnail_format:n \__gotham_unchanged:n
410   },
411   format-framesthumbnail / lower .code:n =
412   {
413     \let\gotham@framesthumbnailformat \text_lowercase:n \%lowercase
414     % \cs_set_eq:NN \__gotham_framesthumbnail_format:n \text_lowercase:n
415     \PackageWarning{ gotham } { Be~aware~that~format~framesthumbnail=lower~can~lead~to~problems. }
416   },
417   format-framesthumbnail / upper .code:n =
418   {
419     \let\gotham@framesthumbnailformat \text_uppercase:n \%uppercase
420     % \cs_set_eq:NN \__gotham_framesthumbnail_format:n \text_uppercase:n
421     \PackageWarning{ gotham } { Be~aware~that~format~framesthumbnail=upper~can~lead~to~problems. }
422   },
423   format-framesthumbnail / titlecase .code:n =
424   {
425     \let\gotham@framesthumbnailformat \text_titlecase_all:n \%Maketitlecase
426     % \cs_set_eq:NN \__gotham_framesthumbnail_format:n \text_titlecase_all:n \%Maketitlecase
427     \PackageWarning{ gotham } { Be~aware~that~format~framesthumbnail=titlecase~can~lead~to~problems. }
428   },
429   format-framesthumbnail / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_
430   }
431 \keys_define:nn { gotham / font }
432 {
433   % shape framesthumbnail
434   shape~framesthumbnail .choice:,
435   shape~framesthumbnail .usage:n = { general },
436   shape~framesthumbnail .default:n = { regular },
437   shape~framesthumbnail / regular .code:n =
438   {
439     \setbeamerfont{framesthumbnail}{shape=\normalfont}
440   },
441   shape~framesthumbnail / smallcaps .code:n =
442   {
443     \setbeamerfont{framesthumbnail}{shape=\scshape}
444   },
445   shape~framesthumbnail / italic .code:n =
446   {
447     \setbeamerfont{framesthumbnail}{shape=\itshape}
448   },

```

```

449 shape~framesubtitle / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_v
450 }
451
452 \keys_define:nn { gotham / font }
453 {
454 % format part
455 format-part .choice:,,
456 format-part .usage:n = { general },
457 format-part .default:n = { regular },
458 format-part / regular .code:n =
459 {
460 \let\gotham@parttitleformat\empty
461 % \cs_set_eq:NN \__gotham_part_title_format:n \text_titlecase:n
462 },
463 format-part / lower .code:n =
464 {
465 \let\gotham@parttitleformat \text_lowercase:n \%lowercase
466 % \cs_set_eq:NN \__gotham_part_title_format:n \text_lowercase:n
467 \PackageWarning{ gotham } { Be~aware~that~format~part=lower~can~lead~to~problems. }
468 },
469 format-part / upper .code:n =
470 {
471 \let\gotham@parttitleformat \text_uppercase:n \%uppercase
472 % \cs_set_eq:NN \__gotham_part_title_format:n \text_uppercase:n
473 \PackageWarning{ gotham } { Be~aware~that~format~part=upper~can~lead~to~problems. }
474 },
475 format-part / titlecase .code:n =
476 {
477 \let\gotham@parttitleformat\text_titlecase_all:n \%Maketitlecase
478 % \cs_set_eq:NN \__gotham_part_title_format:n \text_titlecase:n
479 \PackageWarning{ gotham } { Be~aware~that~format~part=titlecase~can~lead~to~problems. }
480 },
481 format-part / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_value_tl' }
482 }
483 \keys_define:nn { gotham / font }
484 {
485 % shape part
486 shape-part .choice:,,
487 shape-part .usage:n = { general },
488 shape-part .default:n = { regular },
489 shape-part / regular .code:n =
490 {
491 \setbeamertfont{part~title}{shape=\normalfont}

```

```

492 },
493 shape-part / smallcaps .code:n =
494 {
495   \setbeamerfont{part~title}{shape=\scshape}
496 },
497 shape-part / italic .code:n =
498 {
499   \setbeamerfont{part~title}{shape=\itshape}
500 },
501 shape-part / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_value_tl'~is~not~defined~so~it~will~be~ignored. } }
502 }
503
504 \keys_define:nn { gotham / font }
505 {
506   % format section
507   format-section .choice:,
508   format-section .usage:n = { general },
509   format-section .default:n = { regular },
510   format-section / regular .code:n =
511   {
512     \let\gotham@sectiontitleformat\empty
513     % \cs_set_eq:NN \__gotham_section_title_format:n \__gotham_unchanged:n
514   },
515   format-section / lower .code:n =
516   {
517     \let\gotham@sectiontitleformat \text_lowercase:n \%lowercase
518     % \cs_set_eq:NN \__gotham_section_title_format:n \text_lowercase:n
519     \PackageWarning{ gotham } { Be~aware~that~format~section=lower~can~lead~to~problems. }
520   },
521   format-section / upper .code:n =
522   {
523     \let\gotham@sectiontitleformat \text_uppercase:n \%uppercase
524     % \cs_set_eq:NN \__gotham_section_title_format:n \text_uppercase:n
525     \PackageWarning{ gotham } { Be~aware~that~format~section=upper~can~lead~to~problems. }
526   },
527   format-section / titlecase .code:n =
528   {
529     \let\gotham@sectiontitleformat \text_titlecase_all:n \%Maketitlecase
530     % \cs_set_eq:NN \__gotham_section_title_format:n \text_titlecase_all:n
531     \PackageWarning{ gotham } { Be~aware~that~format~section=titlecase~can~lead~to~problems. }
532   },
533   format-section / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_value_~is~not~defined~so~it~will~be~ignored. } }
534 }

```

```

535 \keys_define:nn { gotham / font }
536 {
537   % shape section
538   shape-section .choice:,
539   shape-section .usage:n = { general },
540   shape-section .default:n = { regular },
541   shape-section / regular .code:n =
542   {
543     \setbeamerfont{section~title}{shape=\normalfont}
544   },
545   shape-section / smallcaps .code:n =
546   {
547     \setbeamerfont{section~title}{shape=\scshape}
548   },
549   shape-section / italic .code:n =
550   {
551     \setbeamerfont{section~title}{shape=\itshape}
552   },
553   shape-section / unknown .code:n = { \PackageWarning{ gotham } { The-choice-' \l_keys_value_t
554 }

555 \keys_define:nn { gotham / font }
556 {
557   % format subsection
558   format-subsection .choice:,
559   format-subsection .usage:n = { general },
560   format-subsection .default:n = { regular },
561   format-subsection / regular .code:n =
562   {
563     \let\gotham@subsectiontitleformat\empty
564     % \cs_set_eq:NN \__gotham_subsection_title_format:n \__gotham_unchanged:n
565   },
566   format-subsection / lower .code:n =
567   {
568     \let\gotham@subsectiontitleformat \text_lowercase:n \%lowercase
569     % \cs_set_eq:NN \__gotham_subsection_title_format:n \text_lowercase:n
570     \PackageWarning{ gotham } { Be-aware-that-format-subsection=lower-can-lead-to-problems. }
571   },
572   format-subsection / upper .code:n =
573   {
574     \let\gotham@subsectiontitleformat \text_uppercase:n \%uppercase
575     % \cs_set_eq:NN \__gotham_subsection_title_format:n \text_uppercase:n
576     \PackageWarning{ gotham } { Be-aware-that-format-subsection=upper-can-lead-to-problems. }
577 }
```

```

578 },
579 format-subsection / titlecase .code:n =
580 {
581   \let\gotham@subsectiontitleformat\text_titlecase_all:n \%Maketitlecase
582   % \cs_set_eq:NN \__gotham_subsection_title_format:n \text_titlecase_all:n
583   \PackageWarning{ gotham } { Be~aware~that~format~subsection=titlecase~can~lead~to~problems
584 },
585 format-subsection / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_val
586 }
587 \keys_define:nn { gotham / font }
588 {
589   % shape subsection
590   shape~subsection .choice:,
591   shape~subsection .usage:n = { general },
592   shape~subsection .default:n = { regular },
593   shape~subsection / regular .code:n =
594 {
595     \setbeamerfont{subsection-title}{shape=\normalfont}
596 },
597   shape~subsection / smallcaps .code:n =
598 {
599     \setbeamerfont{subsection-title}{shape=\scshape}
600 },
601   shape~subsection / italic .code:n =
602 {
603     \setbeamerfont{subsection-title}{shape=\itshape}
604 },
605   shape~subsection / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'\l_keys_val
606 }

```

(End of definition for font key - interface. This function is documented on page ??.)

Default_Ufont_Ukeys Apply default key options.

The following test files are used for this code: gotham-test-035.

```

607 % when no value is given, default is called.
608 \keys_set:nn { gotham / font } {
609   format-title, shape-title,
610   format-subtitle, shape~subtitle,
611   format-frametitle, shape~frametitle,
612   format-framesubtitle, shape~framesubtitle,
613   format-part, shape~part,
614   format-section, shape~section,
615   format-subsection, shape~subsection,

```

```
616 }
```

(End of definition for `Default font keys`. This function is documented on page ??.)

`Process_font_keys` Process package options.

The following test files are used for this code: gotham-test-035.

```
617 \ProcessKeyOptions[ gotham / font ]
```

(End of definition for `Process font keys`. This function is documented on page ??.)

```
618 \%endinput
```

```
619 </font>
```

```
620 <*color>
```

```
621 \ProvidesExplPackage{beamercolorthemegotham}{2024-11-11}{1.2.0.a}{Gotham color theme}
```

```
622 \RequirePackage{expl3}
```

```
623 \RequirePackage{xparse}
```

```
624 \RequirePackage{xcolor}
```

COLOR

`\definecolor[named]{gAnthracite}` Definition of the Gotham colors.

`colors_definition`

```
625 \definecolor[named]{gLightOrange}{HTML}{EB811B}
```

```
626 \definecolor[named]{gLightGreen}{HTML}{14B03D}
```

```
627 \definecolor[named]{gDeepBlue}{RGB}{42, 42, 255}
```

```
628 \definecolor[named]{gDeepYellow}{RGB}{255, 204, 0}
```

```
629 \definecolor[named]{gAnthracite}{HTML}{2d3e50}
```

```
630 \definecolor[named]{gLightTeal}{RGB}{172, 195, 210}
```

```
631 \definecolor[named]{gPaleYell}{RGB}{255, 255, 240}
```

```
632 \definecolor[named]{gDarkBlack}{gray}{0.1}
```

```
633 \definecolor[named]{gDarkGrey}{gray}{0.25}
```

```
634 \definecolor[named]{gMidGrey}{gray}{0.5}
```

```
635 \definecolor[named]{gLightGrey}{gray}{0.9}
```

(End of definition for `\definecolor[named]{gAnthracite}` and `colors definition`. These variables are documented on page ??.)

`\colorlet{colorPale}` A set Gotham palette: a list of color variables easily adapted.

`set_gotham_palette_colors`

```
636 % Define the color palette
```

```
637 \@ifundefined{\string\color@colorAreversed}{
```

```
638   % default colorset.
```

```

639  \colorlet{colorPale}{gPaleYell} % BG in light/normal mode
640  \colorlet{colorDark}{gDarkBlack} % FG in light/normal mode
641  \colorlet{colorA}{gAnthracite} % frametitle, standin.out,
642  \colorlet{colorAreversed}{gLightTeal} % frametitle, standin.in,
643  \colorlet{colorB}{gMidGrey} % gray BG : progress bar, blocks
644  \colorlet{colorC}{gDeepYellow} % progress bar
645  \colorlet{colorD}{gLightOrange} % alert
646  \colorlet{colorE}{gLightGreen} % example
647 }{
648  % else nothing to do, colors are already defined.
649 }
650 \providecommand{\gothamHookPostColorBGSet}{}

```

(End of definition for `\colorlet{colorPale}` and set gotham palette colors. These variables are documented on page 27.)

`__gotham_color_set_style_anthracite:`

Command to activate anthracite colorset.

The following test files are used for this code: `gotham-test-1037`.

```

651 \cs_new_protected:Nn \__gotham_color_set_style_anthracite: {
652  \colorlet{colorPale}{gPaleYell} % BG in light/normal mode
653  \colorlet{colorDark}{gDarkBlack} % FG in light/normal mode
654  \colorlet{colorA}{gAnthracite} % frametitle, standin.out,
655  \colorlet{colorAreversed}{gLightTeal} % frametitle, standin.in,
656  \colorlet{colorB}{gMidGrey} % gray BG : progress bar, blocks
657  \colorlet{colorC}{gDeepYellow} % progress bar
658  \colorlet{colorD}{gLightOrange} % alert
659  \colorlet{colorE}{gLightGreen} % example
660 }

```

__gotham_color_set_style_red:

Command to activate red colorset.

The following test files are used for this code: gotham-test-1037.

```
661 \cs_new_protected:Nn \__gotham_color_set_style_red:{  
662   \colorlet{colorPale}{gPaleYell} % BG in light/normal mode  
663   \colorlet{colorDark}{gDarkBlack} % FG in light/normal mode  
664   \colorlet{colorA}{red} % frametitle, standin.out,  
665   \colorlet{colorAreversed}{gLightTeal} % frametitle, standin.in,  
666   \colorlet{colorB}{gMidGrey} % gray BG : progress bar, blocks  
667   \colorlet{colorC}{gDeepYellowr} % progress bar  
668   \colorlet{colorD}{gLightOrange} % alert  
669   \colorlet{colorE}{gLightGreen} % example  
670 }
```

\colorlet{colorBG}{colorPale} A set of variable easily adapted.

set_functional_colors

```
671 % Define the color palette  
672 \colorlet{colorFG}{colorDark}  
673 \colorlet{colorBG}{colorPale}  
674 \colorlet{colorStandin}{colorPale}  
675 \colorlet{colorStandout}{colorA}  
676 \colorlet{colorFrametitle}{colorA}  
677 \colorlet{colorTitlepage}{colorA}  
678 \colorlet{colorFiligrane}{colorB}  
679 \colorlet{colorBackElement}{colorB}  
680 \colorlet{colorProgBar}{colorC}  
681 \colorlet{colorAlert}{colorD}  
682 \colorlet{colorExample}{colorE}
```

(End of definition for \colorlet{colorBG}{colorPale} and set functional colors. These variables are documented on page 27.)

\providebool{darkBG} Variable to track color setup.

\providebool{transparentBG}

```
683 % \providebool{reversedColor}  
684 % \boolefalse{reversedColor}  
685 \providebool{darkBG}  
686 \boolefalse{darkBG}  
687 \providebool{transparentBG}  
688 \booletrue{transparentBG}
```

(End of definition for \providebool{darkBG} and \providebool{transparentBG}. These variables are documented on page ??.)

`__gotham_color_set_darkBG:`

Command to activate dark mode

The following test files are used for this code: gotham-test-037.

```
689 \cs_new_protected:Nn \__gotham_color_set_darkBG:{  
690   \setbeamercolor{normal~text}{%  
691     fg=colorBG,  
692     bg=colorFG,  
693   }%  
694   \usebeamercolor[fg]{normal~text} %  
695   \booltrue{darkBG} %  
696   \boolfalse{transparentBG}  
697   \colorlet{colorFrametitle}{colorAreversed}  
698   \colorlet{colorStandout}{colorAreversed}  
699   \colorlet{colorStandin}{colorFG}  
700   \colorlet{colorTitlepage}{colorAreversed}  
701   % %% adapt and reload  
702   % \colorlet{colorBG}{colorPale}  
703   % \colorlet{colorFG}{colorDark}  
704   % \colorlet{colorFiligrane}{colorB}  
705   % \colorlet{colorBackElement}{colorB}  
706   % \colorlet{colorProgBar}{colorC}  
707   % \colorlet{colorAlert}{colorD}  
708   % \colorlet{colorExample}{colorE}  
709   %% dark  
710   \setbeamercolor{primary~palette}{% reversed color compared to normal text  
711     use=normal~text,  
712     fg=normal~text.bg,  
713     bg=normal~text.fg  
714   }  
715   \gothamHookPostColorBGSet{}  
716 }
```

__gotham_color_set_lightBG:

Command to activate light background.

The following test files are used for this code: gotham-test-037.

```
717 \cs_new_protected:Nn \__gotham_color_set_lightBG:{  
718   \setbeamercolor{normal~text}{  
719     fg=colorFG,  
720     bg=colorBG  
721   }  
722   \usebeamercolor[fg]{normal~text}  
723   \boolfalse{darkBG}  
724   \boolfalse{transparentBG}  
725   \colorlet{colorFrametitle}{colorA}  
726   \colorlet{colorStandout}{colorA}  
727   \colorlet{colorStandin}{colorBG}  
728   \colorlet{colorTitlepage}{colorA}  
729   % %% adapt and reload  
730   % \colorlet{colorBG}{colorPale}  
731   % \colorlet{colorFG}{colorDark}  
732   % \colorlet{colorFiligrane}{colorB}  
733   % \colorlet{colorBackElement}{colorB}  
734   % \colorlet{colorProgBar}{colorC}  
735   % \colorlet{colorAlert}{colorD}  
736   % \colorlet{colorExample}{colorE}  
737   %% light  
738   \setbeamercolor{primary~palette}{  
739     % reversed color compared to normal text  
740     use=normal~text,  
741     fg=normal~text.bg,  
742     bg=normal~text.fg  
743   }  
744   \gothamHookPostColorBGSet{}  
745 }
```

__gotham_color_set_transparentBG:

Command to activate transparent background.

The following test files are used for this code: gotham-test-037.

```
746 % \providecommand{\gotham@colors@transparent}{
747 \cs_new_protected:Nn \__gotham_color_set_transparentBG: {
748   \setbeamercolor{normal~text}{%
749     fg=colorFG,
750     bg=,
751   }
752   \usebeamercolor[fg]{normal~text}
753   \boolfalse{darkBG}
754   \booltrue{transparentBG}
755   \colorlet{colorFrametitle}{colorA}
756   \colorlet{colorStandout}{colorA}
757   {\usebeamercolor[bg]{normal~text}\colorlet{colorStandin}{bg}}% this is not working because
758   % \usebeamercolor{normal~text} % reset % NOT working neither
759   \colorlet{colorStandin}{colorBG} % since the two previous lines are not working, let define
760   \colorlet{colorTitlepage}{colorA}
761   % %%% adapt and reload
762   % \colorlet{colorBG}{colorPale}
763   % \colorlet{colorFG}{colorDark}
764   % \colorlet{colorFiligrane}{colorB}
765   % \colorlet{colorBackElement}{colorB}
766   % \colorlet{colorProgBar}{colorC}
767   % \colorlet{colorAlert}{colorD}
768   % \colorlet{colorExample}{colorE}
769   %%% like light background.
770   \setbeamercolor{primary~palette}{%
771     % reversed color compared to normal text
772     use=normal~text,
773     fg=colorBG,
774     bg=normal~text.fg
775   }
776   \gothamHookPostColorBGSet{}
777 }
```

__gotham_color_set_transparent_block:

Command to activate transparent block.

The following test files are used for this code: gotham-test-037.

```
778 \cs_new_protected:Nn \__gotham_color_set_transparent_block: {
779   \setbeamercolor{block~title}{%
780     use=normal~text,
781     fg=normal~text.fg,
782     bg=
783   }
784   \setbeamercolor{block~body}{%
785     bg=
786   }
787   \setbeamercolor{alerted~text}{%
788     fg=colorAlert
789   }
790   \setbeamercolor{example~text}{%
791     fg=colorExample
792   }
793   \setbeamercolor{block~title-example}{%
794     use={block~title, example~text},
795     bg=block~title.bg,
796     fg=example~text.fg
797   }
798   \setbeamercolor{block~title-alerted}{%
799     use={block~title, alerted~text},
800     bg=block~title.bg,
801     fg=alerted~text.fg
802   }
803 }
```

__gotham_color_set_fill_block:

Command to activate fill block.

The following test files are used for this code: gotham-test-037.

```
804 \cs_new_protected:Nn \__gotham_color_set_fill_block:{  
805   \setbeamercolor{block~title}{  
806     fg=colorBackElement!10!normal~text.fg,  
807     bg=colorBackElement!135!fg  
808   }  
809   \setbeamercolor{block~body}{  
810     use={block~title, normal~text},  
811     bg=block~title.bg!50!normal~text.bg  
812   }  
813   \setbeamercolor{alerted~text}{  
814     fg=colorAlert  
815   }  
816   \setbeamercolor{example~text}{  
817     fg=colorExample  
818   }  
819   \setbeamercolor{block~title-example}{  
820     use={block~title, example~text},  
821     bg=block~title.bg,  
822     fg=example~text.fg  
823   }  
824   \setbeamercolor{block~title-alerted}{  
825     use={block~title, alerted~text},  
826     bg=block~title.bg,  
827     fg=alerted~text.fg  
828   }  
829 }
```

`__gotham_color_set_native_block:`

Command to activate native block.

The following test files are used for this code: gotham-test-037.

```
830 \cs_new_protected:Nn \__gotham_color_set_native_block: {
831   \setbeamercolor{block~title}{%
832     fg=colorPale,
833     bg=colorBackElement!90!fg
834   }
835   \setbeamercolor{block~body}{%
836     use={block~title, normal~text},
837     bg=block~title.bg!50!normal~text.bg
838   }
839   \setbeamercolor{alerted~text}{%
840     fg=colorAlert
841   }
842   % With native block, we have to let alerted text with a visible color (not pale) to keep all
843   % So, we have to create an extra color: alertedBlock~text.
844   \setbeamercolor{alertedBlock~text}{%
845     fg=colorPale
846   }
847   \setbeamercolor{example~text}{%
848     fg=colorPale
849   }
850   \setbeamercolor{block~title~alerted}{%
851     use={block~title, alertedBlock~text},
852     bg=colorAlert,
853     fg=alertedBlock~text.fg
854   }
855   \setbeamercolor{block~title~example}{%
856     use={block~title, example~text},
857     bg=colorExample,
858     fg=example~text.fg
859   }
860 }
```

`Gotham_color_adaptation` Set colors variable from Gotham color setup that needs specific adaptation, i.e. `structure` as mentioned in Beamer documentation and `progress bar` since it is a new feature.

The following test files are used for this code: gotham-test-037.

```
861 \setbeamercolor{structure}{use=normal~text, fg=normal~text.fg}
```

```

862 \setbeamercolor{progress~bar}{
863   use=alerted~text,
864   fg=colorProgBar,
865   bg=alerted~text.fg!50!black!30
866 }

```

(End of definition for Gotham color adaptation. This function is documented on page ??.)

- `Usual_color_env` Set colors variable from Gotham color setup. The titles and structural elements (e.g. `itemize` bullets) are set in the same color as `normal text`. This would ideally done by setting `normal text` as a parent style, which we do to set `titlelike`, but this doesn't work for `structure` as its foreground is set explicitly in `beamercolorthemedefault.sty`.

The following test files are used for this code: gotham-test-037.

```

867 \setbeamercolor{titlelike}{use=normal~text, parent=normal~text}
868 \setbeamercolor{author}{use=normal~text, parent=normal~text}
869 \setbeamercolor{date}{use=normal~text, parent=normal~text}
870 \setbeamercolor{institute}{use=normal~text, parent=normal~text}
871 \setbeamercolor{frametitle}{
872   use=primary~palette,
873   parent=primary~palette,
874   bg=colorFrametitle
875 }
876 % The Gotham inner or outer themes optionally display progress bars in various locations.
877 % Their color is set by |progress bar| but the two different kinds can be customized separately.
878 % The horizontal rule on the title page is also set based on the progress bar color and can
879 \setbeamercolor{title~separator}{
880   use=progress~bar,
881   parent=progress~bar
882 }
883 \setbeamercolor{progress~bar~in~head/foot}{%
884   use=progress~bar,
885   parent=progress~bar
886 }
887 \setbeamercolor{progress~bar~in~part~page}{%
888   use=progress~bar,
889   parent=progress~bar
890 }
891 \setbeamercolor{progress~bar~in~section~page}{%
892   use=progress~bar,
893   parent=progress~bar
894 }
895 \setbeamercolor{progress~bar~in~splitvert}{%

```

```

896   use=progress~bar,
897   parent=progress~bar
898 }
899 % \setbeamercolor{progress~bar~in~subsection~page}{
900 %   use=progress~bar,
901 %   parent=progress~bar
902 %
903 % \setbeamercolor{progress~bar~in~subsubsection~page}{
904 %   use=progress~bar,
905 %   parent=progress~bar
906 %
907 %
908 % Blocks
909 \setbeamercolor{block~body~alerted}{use=block~body, parent=block~body}
910 \setbeamercolor{block~body~example}{use=block~body, parent=block~body}
911 %
912 % Footnote
913 \setbeamercolor{footnote}{fg=normal~text.fg!90}
914 \setbeamercolor{footnote~mark}{fg=.}
915 %
916 % Bibliography
917 %
918 % We also reset the bibliography colors in order to pick up the surrounding colors at the ti
919 % This prevents us having to set the correct color in normal and standout mode.
920 \setbeamercolor{bibliography entry author}{fg=, bg=}
921 \setbeamercolor{bibliography entry title}{fg=, bg=}
922 \setbeamercolor{bibliography entry location}{fg=, bg=}
923 \setbeamercolor{bibliography entry note}{fg=, bg=}

```

(End of definition for *Usual color env*. This function is documented on page ??.)

`new_color_environments` Set up colors for the the new beamer environment used by the theme.

The following test files are used for this code: gotham-test-037.

```

924 % \setbeamercolor{frametitleSection}{use=primary-palette, bg=, fg=primary~palette.bg}
925 \setbeamercolor{frametitleSection}{use=structure, fg=structure.bg}
926
927 \setbeamercolor{standout}{use=primary-palette, bg=colorStandout, fg=primary~palette.bg}
928 \setbeamercolor{standin}{use=normal~text, bg=colorStandin, fg=normal~text.fg}
929
930 \setbeamercolor{section~in~toc}{use=normal~text, parent=normal~text,}
931 \setbeamercolor{subsection~in~toc}{use=normal~text, parent=normal~text,}
932 \setbeamercolor{subsubsection~in~toc}{use=normal~text, parent=normal~text,}
933 \setbeamercolor{footlineRule}{use=normal~text, parent=normal~text,}

```

(End of definition for new color environments. This function is documented on page ??.)

`color_key_interface` Controls the background mode (dark, light or transparent background) and the block (fill or transparent) and colorset (anthracite, red, blue, green, etc).

The following test files are used for this code: gotham-test-037.

```
934 \keys_define:nn { gotham / color }
935 {
936   % block
937   block .choice:, 
938   block .usage:n = { general },
939   block .default:n = { native },
940   block / native .code:n = { \__gotham_color_set_native_block: },
941   block / transparent .code:n = { \__gotham_color_set_transparent_block: },
942   block / fill .code:n = { \__gotham_color_set_fill_block: },
943   block / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'`l_keys_value_tl'~is~un-
944 }

945
946 \keys_define:nn { gotham / color }
947 {
948   % background
949   background .choice:, 
950   background .usage:n = { general },
951   background .default:n = { transparent },
952   background / transparent .code:n = { \__gotham_color_set_transparentBG: },
953   background / light .code:n = { \__gotham_color_set_lightBG: },
954   background / dark .code:n = { \__gotham_color_set_darkBG: },
955   background / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'`l_keys_value_tl'~is~un-
956 }

957
958 \keys_define:nn { gotham / color }
959 {
960   % colorset
961   colorset .choice:, 
962   colorset .usage:n = { general },
963   colorset .default:n = { anthracite },
964   colorset / anthracite .code:n = { \__gotham_color_set_style_anthracite: },
965   colorset / red .code:n = { \__gotham_color_set_style_red: },
966   % colorset / blue .code:n = { },
967   % colorset / green .code:n = { },
968   % colorset / orange .code:n = { },
969   % colorset / teal .code:n = { },
970   colorset / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'`l_keys_value_tl'~is~un-
```

```
971 }
```

(End of definition for `color key - interface`. This function is documented on page ??.)

`Default_color_keys` Apply default key options.

The following test files are used for this code: `gotham-test-037`.

```
972 % when no value is given, default is called.  
973 \keys_set:nn { gotham / color } { background, block, colorset }
```

(End of definition for `Default color keys`. This function is documented on page ??.)

`Process_color_keys` Process package options.

The following test files are used for this code: `gotham-test-037`.

```
974 \ProcessKeyOptions[ gotham / color ]  
975 \mode<all>
```

(End of definition for `Process color keys`. This function is documented on page ??.)

```
976 \%endinput  
977 </color>
```

```
978 <*inner>  
979 \ProvidesExplPackage{beamerinnerthemegotham}{2024-11-11}{1.2.0.a}{gotham inner theme}  
980 \RequirePackage{expl3}  
981 \RequirePackage{xparse}  
982 \RequirePackage{calc}  
983 \RequirePackage{tikz}
```

INNER

A `beamer` inner theme dictates the style of the frame elements traditionally set in the “body” of each slide. These include:

- title page;
- backgrounds;
- standin/out;
- part, section etc, pages;
- table of content pages (including for sections...);
- environement elements:

- itemize, enumerate, and description environments;
- block environments including theorems and proofs;
- figures and tables; and
- footnotes and plain text.

Titlepage

`Compatibilitymodeforcolors` FROM COLOR THEME: useful to provide this recall when the inner theme is loaded without the color theme.

```

984 \@ifundefined{\string\color@colorProgBar}{
985   \providebool{darkBG} \boolfalse{darkBG}
986   \providebool{transparentBG} \booltrue{transparentBG}
987   \colorlet{colorBG}{white}
988   \colorlet{colorFG}{black}
989   \colorlet{colorFrametitle}{purple}
990   \colorlet{colorStandout}{purple}
991   \colorlet{colorStandin}{purple}
992   \colorlet{colorTitlepage}{purple}
993   \colorlet{colorFiligrane}{gray}
994   \colorlet{colorBackElement}{gray}
995   \colorlet{colorProgBar}{orange}
996   \colorlet{colorAlert}{red}
997   \colorlet{colorExample}{green}
998   \setbeamercolor{progress~bar}{
999     use=alerted~text,
1000     fg=colorProgBar,
1001     bg=alerted~text.fg!50!black!30
1002   }
1003   \setbeamercolor{progress~bar~in~head/foot}{%
1004     use=progress~bar,
1005     parent=progress~bar
1006   }
1007   \setbeamercolor{progress~bar~in~part~page}{%
1008     use=progress~bar,
1009     parent=progress~bar
1010   }
1011   \setbeamercolor{progress~bar~in~section~page}{%
1012     use=progress~bar,
1013     parent=progress~bar
1014   }
1015   \setbeamercolor{progress~bar~in~splitvert}{%
1016     use=progress~bar,

```

```

1017     parent=progress-bar
1018 }
1019 \setbeamercolor{frametitleSection}{use=primary-palette, bg=, fg=primary-palette.bg}
1020 \setbeamercolor{standout}{use=primary-palette, bg=colorStandout, fg=primary-palette.bg}
1021 \setbeamercolor{standin}{use=normal-text, bg=colorStandin, fg=normal-text.fg}
1022 \setbeamercolor{section-in-toc}{use=normal-text, parent=normal-text,}
1023 \setbeamercolor{subsection-in-toc}{use=normal-text, parent=normal-text,}
1024 \setbeamercolor{subsubsection-in-toc}{use=normal-text, parent=normal-text,}
1025 }{
1026 % else the colors are defined: this is fine.
1027 }

```

(End of definition for *Compatibility mode for colors*. This function is documented on page ??.)

\maketitle Normal people should use \maketitle or \titlepage instead of using the title page
 \titlepage beamer template directly. Beamer already defines these macros, but we patch them here
 to make the title page [plain] by default, remove \@thanks, and ensure the title frame
 number doesn't count. Inserts the title frame, or causes the current frame to use the
 title page template.

The following test files are used for this code: gotham-test-038.

```

1028 \def\maketitle{
1029   \ifbeamer@inframe
1030     \titlepage
1031   \else
1032     \frame[plain, c, noframenumbering]{\titlepage}
1033   \fi
1034 }
1035 \def\titlepage{
1036   % \setkeys{beamerframe}{c} % no effect
1037   % \setkeys{beamerframe}{plain} % no effect
1038   % \setbeamertemplate{footline}[empty] % no effect
1039   % \setkeys{beamerframe}{nofootline} % create error of unclosed env
1040   \usebeamertemplate{title-page}
1041 }

```

(End of definition for \maketitle and \titlepage. These functions are documented on page ??.)

\defbeamertemplate{title-graphic}{gotham} Definition of elements templates that will be used in titlepage.

The following test files are used for this code: gotham-test-038.

```

1042 \defbeamertemplate*{title-graphic}{gotham}{
1043   % \vbox to Opt {%
1044   %% MODIFIED !

```

```

1044 \vbox{
1045   % \vspace*{2em} %%%% COMMENT ADDED !
1046   \inserttitlegraphic
1047 }
1048 \nointerlineskip
1049 }
1050 \defbeamertemplate*{title}{gotham}{
1051   \%raggedright% %%%% COMMENT ADDED !
1052   \linespread{1.0}
1053   \inserttitle
1054   \par
1055   \vspace*{0.5em}
1056 }
1057 \defbeamertemplate*{subtitle}{gotham}{
1058   \%raggedright% %%%% COMMENT ADDED !
1059   \insertsubtitle
1060   \par
1061   \vspace*{0.5em}
1062 }
1063 \defbeamertemplate*{author}{gotham}{
1064   \vspace*{1.em}
1065   \insertauthor
1066   \par
1067   \vspace*{0.25em}
1068 }
1069 \defbeamertemplate*{date}{gotham}{
1070   \insertdate
1071   \par
1072 }
1073 \defbeamertemplate*{institute}{gotham}{
1074   \vspace*{3mm}
1075   \insertinstitute
1076   \par
1077 }

```

(End of definition for `\defbeamertemplate{title~graphic}{gotham}`. This function is documented on page ??.)

Define the new lengths that will be used for titlepage templates.

```

\l_gotham_titleseparator_width_dim
\l_gotham_titleseparator_height_dim
\l_gotham_title_width_dim
\l_gotham_subtitle_width_dim
\l_gotham_title_max_width_dim
1078 \dim_new:N \l_gotham_titleseparator_width_dim
1079 \dim_set:Nn \l_gotham_titleseparator_width_dim {\textwidth}
1080 \dim_new:N \l_gotham_titleseparator_height_dim
1081 \dim_set:Nn \l_gotham_titleseparator_height_dim {2pt}

```

```

1082 % \newlength{\titlewidth}
1083 % \newlength{\subtitlewidth}
1084 % \newlength{\maxwidth}
1085 \dim_new:N \l__gotham_title_width_dim
1086 \dim_new:N \l__gotham_subtitle_width_dim
1087 \dim_new:N \l__gotham_title_max_width_dim

```

(End of definition for `\l__gotham_titleseparator_width_dim` and others.)

`\defbeamertemplate*{title-separator}{gotham}` Define a new template for “line” displayed on some titlepage templates.

```

1088 \defbeamertemplate*{title-separator}{gotham}{
1089   \begin{tikzpicture}
1090     \fill[fg] (0,0) rectangle (\gotham@titleseparator@linewidth, \gotham@titleseparator@lineheight);
1091     \fill[fg] (0,0) rectangle
1092       (\dim_use:N \l__gotham_titleseparator_width_dim,
1093        \dim_use:N \l__gotham_titleseparator_height_dim);
1094   \end{tikzpicture}
1095   \par
1096 }

```

(End of definition for `\defbeamertemplate*{title-separator}{gotham}`. This variable is documented on page ??.)

`\gothamtitlepagelogo` The following test files are used for this code: `gotham-test-038`.

```
1097 \providecommand{\gothamtitlepagelogo}{}%
```

(End of definition for `\gothamtitlepagelogo`. This variable is documented on page [28](#).)

`\gothamtitlepagebg` The following test files are used for this code: `gotham-test-038`.

```
1098 \providecommand{\gothamtitlepagebg}{}%
```

(End of definition for `\gothamtitlepagebg`. This variable is documented on page [28](#).)

`\defbeamertemplate{title-page}{gotham-normal}` Template for the normal gotham title page. Each element is only typeset if it is defined by the user. If `\subtitle` is empty, for example, it won’t leave a blank space on the title slide.

The following test files are used for this code: `gotham-test-038`.

```

1099
1100 % Beamer's definition of |\insertauthor| is always nonempty, so we have to test another macro
1101 % This solution was suggested by Sam Carter in an answer to \href{https://tex.stackexchange.com/q/113333/128}
1102

```

```

1103 \defbeamertemplate{title~page}{gotham-normal}{
1104   \ifx\insertframetitle\empty\else\vspace*{-3em}\fi
1105   \begin{picture}(0,0)
1106     % The text: title, author, institute, etc.
1107     \put(-30,-125){\noindent
1108       \fcolorbox{normal-text.bg}{normal-text.bg}{%
1109         \begin{minipage}[b][\paperheight][\paperwidth]
1110           \parbox[c][0pt][c]{0pt}{\gothamtitlepagebg}
1111           \centering
1112           \vfill
1113           \ifx\inserttitle\empty\else
1114             \parbox{0.9\textwidth}{\centering
1115               \usebeamertemplate*{title}
1116             }\\[1.ex]
1117           \fi
1118           \ifx\insertsubtitle\empty\else
1119             \parbox{0.9\textwidth}{\centering
1120               \usebeamertemplate*{subtitle}
1121             }\\[2.ex]
1122           \fi
1123           % \hspace*{-0pt}
1124           \usebeamertemplate*{title-separator}
1125           % from above patch
1126           \expandafter\ifblank\expandafter{\beamer@andstripped}{%
1127             % empty author
1128             \vspace*{1.em}
1129           }{
1130             \usebeamertemplate*{author}
1131           }
1132           % \ifx\insertauthor\empty Empty-Author\else TT \fi
1133           \ifx\insertdate\empty\else\usebeamertemplate*{date}\fi
1134           \ifx\insertinstitute\empty\else\parbox{0.9\textwidth}{\raggedright\usebeamertemplate*{institute}}\fi
1135           \vfill
1136           \vbox{}
1137           \end{minipage}
1138         }
1139         % end third argument of fcolorbox
1140       }
1141       % the institute logo on title page
1142       \put(234,-120){
1143         \gothamtitlepagelogo
1144       }
1145 
```

```

1146
1147 % the extra logos on title page (\inserttitlegraphic)
1148 \put(-27,-123){
1149   \noindent\vbox{
1150     \begin{minipage}[b][0.96\paperheight]{0.899\textwidth}
1151       \ifx\inserttitlegraphic\empty\else\usebeamertemplate*{title~graphic}\fi
1152     \end{minipage}
1153   }
1154 }
1155 \end{picture}
1156 }

```

(End of definition for \defbeamertemplate{title~page}{gotham~normal}. This function is documented on page ??.)

beamertemplate{title~page}{gotham~reversed} With a similarly layout to gotham normal, but this template inverses the background and foreground colors compared to the color mode chose (dark, light or transparent).

The following test files are used for this code: gotham-test-038.

```

1157 \defbeamertemplate{title~page}{gotham~reversed}{
1158   \begin{picture}(0,0)
1159     % The background picture
1160     \put(-28,-128){\gothamtitlepagebg}
1161
1162     % The text: title, author, institute, etc.
1163     \put(-4,-125){\noindent
1164       % \fcolorbox{declared-color-frame}{declared-color-background}{text}
1165       \ifbool{darkBG}{%
1166         % Dark true
1167         \setbeamercolor{normal~text}{fg=colorFG, }
1168         \fcolorbox{colorPale}{colorPale}{% reversed
1169       }{%
1170         % Light
1171         \setbeamercolor{normal~text}{fg=colorBG, }
1172         \fcolorbox{colorTitlepage}{colorTitlepage}{% reversed
1173       }% end if
1174     {
1175       % begin third argument of fcolorbox
1176       \%fcolorbox{normal~text.fg}{normal~text.fg}{%
1177         \begin{minipage}[b][\paperheight]{\textwidth}
1178           \centering
1179           \vfill
1180           \ifx\inserttitle\empty\else\usebeamertemplate*{title}\fi
1181           \ifx\insertsubtitle\empty\else\usebeamertemplate*{subtitle}\fi

```

```

1182     \usebeamertemplate*{title~separator}
1183     \expandafter\ifblank\expandafter{\beamer@andstripped}{%
1184         % empty author
1185         \vspace*{1.em}
1186     }{%
1187         \usebeamertemplate*{author}
1188     }
1189     \ifx\insertdate\empty\else\usebeamertemplate*{date}\fi
1190     \ifx\insertinstitute\empty\else\parbox{0.9\textwidth}{\raggedright\usebeamertemplate*{%
1191         \vfill
1192         \vbox{}%
1193     }\end{minipage}%
1194     }%
1195     % end third argument of fcolorobx
1196 }
1197
1198 % the institute logo on title page
1199 \put(234,-120){
1200     \gothamtitlepagelogo
1201 }
1202
1203 % the extra logos on title page (\inserttitlegraphic)
1204 \put(-27,-123){
1205     \noindent\vbox{
1206         \begin{minipage}[b][0.96\paperheight]{0.899\textwidth}
1207             \ifx\inserttitlegraphic\empty\else\usebeamertemplate*{title~graphic}\fi
1208         \end{minipage}%
1209     }%
1210 }
1211 \end{picture}
1212 }

```

(End of definition for \defbeamertemplate{title~page}{gotham-reversed}. This function is documented on page ??.)

amertemplate{title-page}{gotham-dividedpic} This title page template is inspired from <https://github.com/LukasPietzschmann/awesome-beamer>

The following test files are used for this code: gotham-test-038.

```

1213 \defbeamertemplate{title~page}{gotham~dividedpic}{%
1214     \long\def\tmpEmpty{}%
1215     \def\titlecontent{\usebeamertfont{title}\usebeamercolor[fg]{title}\inserttitle}%
1216     \def\subtitlecontent{\usebeamertfont{subtitle}\usebeamercolor[fg]{subtitle}\insertsubtitle}%
1217     \settowidth\l__gotham_title_width_dim\titlecontent

```

```

1218 \settowidth\l__gotham_subtitle_width_dim\subtitlecontent
1219 \setlength\l__gotham_title_max_width_dim{\ifdim\l__gotham_title_width_dim>\l__gotham_subtitle_width_dim\else\l__gotham_subtitle_width_dim\fi}
1220 % \thispagestyle{navigation@titlepage}
1221 \begin{minipage}{.55\textwidth}
1222   \raggedright
1223   \titlecontent\\
1224   \subtitlecontent\\
1225   % \textcolor{accent}{\rule{\ifdim\l__gotham_title_max_width_dim<.55\textwidth\l__gotham_subtitle_width_dim\else\l__gotham_subtitle_width_dim\fi}{.55\textwidth\l__gotham_subtitle_width_dim\fi}}
1226   \textcolor{colorProgBar}{\rule{\ifdim\l__gotham_title_max_width_dim<.55\textwidth\l__gotham_subtitle_width_dim\else\l__gotham_subtitle_width_dim\fi}{.55\textwidth\l__gotham_subtitle_width_dim\fi}}
1227   \usebeamertemplate{author}\usebeamercolor[fg]{author}
1228   \insertauthor\\
1229   % \ifx\insertauthor\empty\else
1230   \expandafter\ifblank\expandafter{\beamer@andstripped}{%
1231     % empty author
1232     \vspace*{1.em}%
1233   }{%
1234     \usebeamertemplate{author}\usebeamercolor[fg]{author}
1235     \insertshortauthor
1236     \vspace{2em}%
1237   }
1238 % \fi
1239 \ifx\insertinstitute\empty\else%
1240   \usebeamertemplate*{institute}\vspace{2em}%
1241 \fi
1242 \insertdate
1243 \end{minipage}

1244 % \ifdefined\@background
1245 \begin{tikzpicture}[remember picture, overlay]
1246   \clip (current-page.south-east)
1247     -- (current-page.north-east)
1248     -- ++(-5.1, 0)
1249     -- ++(-3, -\paperheight)
1250     -- cycle;
1251
1252 \ifx\gothamtitlepagebg\tmpEmpty
1253   \fill[
1254     % path fading=title~page~picture~fading,
1255     % left color=\ifbool{darkBG}{colorDark!200}{colorPale!100},
1256     right color=colorTitlepage!100,%\ifbool{darkBG}{colorPale!100}{colorDark!100},
1257     % fading angle=-15,
1258   ]
1259   (current-page.south-east)

```

```

1261     rectangle
1262     ++(\dimexpr-0.55\paperwidth, \dimexpr\paperheight+1cm);
1263 \else
1264   \node[
1265     anchor=south-east,
1266     inner sep=0,
1267     outer sep=0
1268   ] at (current-page.south-east) {
1269     % \includegraphics[height=\paperheight]{\@background}
1270     \gothamtitlepagebg
1271   };
1272 \fi
1273 \end{tikzpicture}
1274 }

```

(End of definition for `\defbeamertemplate{title-page}{gotham-dividedpic}`. This function is documented on page ??.)

`\beamertemplate{title-page}{gotham-splitvert}` This title page template is inspired from <https://github.com/pcafrica/focus-beamertheme>

The following test files are used for this code: `gotham-test-038`.

```

1275 \defbeamertemplate{title-page}{gotham-splitvert}{
1276   % \IfEmpty{\insertframetitle}{%
1277   \ifx\beamer@frametitle\empty
1278     \vspace*{-0.5\paperheight}
1279   \else %
1280     \vspace*{-0.63\paperheight}
1281   \fi %
1282   {
1283     \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}%
1284     \begin{tikzpicture}[overlay, remember picture]
1285       \fill[color=gotham@@tempColor] (current-page.north-west) rectangle ([shift = {(0, -0.45\paperheight)}] current-page.south);
1286     \end{tikzpicture}
1287   }
1288   % \vspace{1.65\baselineskip}
1289   \begin{minipage}[b][0.5\paperheight]{\textwidth}
1290     % \vspace{\baselineskip}
1291     \vbox{%
1292       \vfill
1293       {
1294         \usebeamertfont{title}
1295         \usebeamercolor[fg]{frametitle}
1296         \inserttitle
1297       }
1298     }
1299   
```

```

1298 }
1299 \ifx\insertsubtitle\empty\else
1300   \\[1ex]
1301 {
1302   \usebeamerfont{subtitle}
1303   \usebeamercolor[fg]{frametitle}
1304   \insertsubtitle
1305 }
1306 \fi
1307 \vspace{1.\baselineskip}
1308 \end{minipage}

1309
1310
1311 % Set the title graphic in a zero-height box, so that
1312 % the position of other elements is not affected.
1313 \ifx\inserttitlegraphic\empty\else
1314   \newline
1315   \vspace*{-1.65\baselineskip}
1316   % {\vfuzz=9999pt\vbox~to~0pt {
1317   {\parbox[c][0pt][c]{\textwidth}{%
1318     \raggedleft
1319     \inserttitlegraphic
1320     % \usebeamertemplate*{title~graphic}
1321   }}
1322 \fi
1323
1324 % \ifx\insertauthor\empty\else
1325 \expandafter\ifblank\expandafter{\beamer@andstripped}%
1326   % empty author
1327   \vspace*{1.em}
1328 }{
1329   \newline
1330   \begin{minipage}[t]{\textwidth}
1331     % \usebeamercolor{normal~text}
1332     % \usebeamerfont{author}
1333     % \insertauthor
1334     \vspace*{-0.65\baselineskip}
1335     \usebeamertemplate*{author}
1336   \end{minipage}
1337 }
1338 % \fi
1339
1340 \ifx\insertinstitute\empty\else

```

```

1341   \newline
1342   \vspace*{-1.65\baselineskip}
1343   \begin{minipage}[t]{\textwidth}
1344     % \usebeamerfont{institute}
1345     % \insertinstitute
1346     \usebeamertemplate*{institute}
1347   \end{minipage}
1348 \fi
1349
1350 \ifx\insertdate\empty\else
1351   \newline
1352   \begin{minipage}[t]{\textwidth}
1353     \vspace*{2.65\baselineskip}
1354     % \usebeamerfont{date}
1355     % \insertdate
1356     \usebeamertemplate*{date}
1357   \end{minipage}
1358   \vspace*{-3.15\baselineskip}
1359 \fi
1360 }

```

(End of definition for `defbeamertemplate{title-page}{gotham-splitvert}`. This function is documented on page ??.)

```
\__gotham_set_template:nn #1 : element name (from beamer doc) in other word, the name the template category
#2 : prefined option (from beamer doc)
```

Function to set a beamertemplate with an option if it exists, otherwise an error is raised.
Unfortunatly, (as far as I know) it not possible to test if the element name exists independently from the prefined option.

The following test files are used for this code: gotham-test-038.

```
1361 \cs_if_exist:NTF \__gotham_set_template:nn {}{
1362   % If it doesn't exist, then create it.
1363
1364   % Define the command to set template if it exists.
1365   \cs_new_protected:Nn \__gotham_set_template:nn
1366   {
1367     \cs_if_exist:cTF {beamer@@tmpop@#1#2} {
1368       \setbeamertemplate{#1}[#2]
1369     }{
1370       \PackageError{beamerinnerthemegotham}
1371       {The-beamer~template~named~'#1'~with~the~option~'#2'~does~not~exist}
1372       {helping~message unknown setbeamertemplate option}
1373     }
1374   }
1375 }
```

inner_key_-_interface Controls for the title page templates.

The following test files are used for this code: gotham-test-038.

```
1376 \keys_define:nn { gotham / inner }
1377 {
1378   % title-page
1379   title-page .usage:n = { general },
1380   title-page .default:n = { gotham-normal },
1381   title-page .code:n = { \__gotham_set_template:nn{title-page}{#1} },
1382 }
```

(End of definition for inner key - interface. This function is documented on page ??.)

Backgrounds

```
1383 % Background lengths
1384 % \newlength{\imageBGoffset}
1385 % \setlength{\imageBGoffset}{\paperwidth}
1386 % \addtolength{\imageBGoffset}{-8.5mm}
```

\l__gotham_template_name_prop Dictionary/map of template elements and predefined option according to the context.
Naming convention: template/What/Who, i.e. Name: key=background canvas/watermark, value = gotham draft

```

1387 \prop_if_exist:NTF \l__gotham_template_name_prop
1388 {}{
1389   % if not defined than define it.
1390   \prop_new:N \l__gotham_template_name_prop
1391 }
```

(End of definition for \l__gotham_template_name_prop.)

amertemplate{background~canvas}{empty}{def} empty background canvas that contains color, that can be used to reset background.

The following test files are used for this code: gotham-test-038.

```

1392 \defbeamertemplate{background~canvas}{empty}{% empty background style has a color.
1393   % \ifbeamercolorempty [bg]{background}{}{\color{bg}\vrule width\paperwidth height\paperheight
1394   \hspace*{28pt}
1395   \begin{beamercolorbox}[wd=\paperwidth,
1396     ht=\paperheight,
1397   ]{background}
1398     % nothing to write, only a background color
1399   \end{beamercolorbox}
1400 }%
1401 \defbeamertemplate{background}{empty}{}
```

(End of definition for \defbeamertemplate{background~canvas}{empty}{def}. This function is documented on page ??.)

te{background}{watermark/gotham-draft}{def} Background that contains a watermark stamp with the word: DRAFT.

The following test files are used for this code: gotham-test-038.

```

1402 \defbeamertemplate{background}{watermark/gotham-draft}{
1403   \begin{tikzpicture}[overlay,remember picture]
1404     \node [color=red, opacity=0.3, scale=5, rotate=45] at ([shift={(0,0)}]current-page.center)
1405   \end{tikzpicture}
1406 }
1407 % Add the template to the prop (dictionary)
1408 \prop_put:Nnn \l__gotham_template_name_prop {background/watermark} {gotham-draft}
```

(End of definition for \defbeamertemplate{background}{watermark/gotham-draft}{def}. This function is documented on page ??.)

__gotham_add_beamerframe_key:n

#1 : Name of the option to add, this name should also correspond to the name of the environment followed by the suffix 'env'.

Function to add an option of a frame using an environment. For example, if the name 'optionA' is the argument given to the function, an frame option named 'optionA' will be added, and this option will surround the frame with the environment named 'optionAenv'. So, the environment 'optionA' must have been declared before.

The following test files are used for this code: gotham-test-038.

```
1409 \seq_if_exist:NTF \l__gotham_frameoption_tmp_seq {}{  
1410   % Define the sequence of frameoptions environments to close  
1411   \seq_new:N \l__gotham_frameoption_tmp_seq  
1412 }  
1413  
1414 \cs_if_exist:NTF \__gotham_add_beamerframe_key:n {}{  
1415   % if it doesn't exist, then create it.  
1416  
1417   % Define the command to add frameoptions  
1418   \cs_new_protected:Nn \__gotham_add_beamerframe_key:n {  
1419     \define@key{beamerframe}{#1 }[true]{  
1420       \begin{#1env}  
1421         \seq_put_left:Nn \l__gotham_frameoption_tmp_seq { \end{#1env} }  
1422       }  
1423     }  
1424  
1425   % At the end of frames close the opened environments.  
1426   \apptocmd{\beamer@reseteecodes}{  
1427     % Join elements in the queue without separator then output the result  
1428     \seq_use:Nn \l__gotham_frameoption_tmp_seq {}  
1429     % clear working queue  
1430     \seq_clear:N \l__gotham_frameoption_tmp_seq  
1431   }{}{  
1432 }
```

\begin{frame}[noBCG] Add a frame option noBCG to display an empty background canvas. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-038.

```
1433  
1434 \newenvironment{noBGEnv}{
```

```

1435   \setbeamertemplate{background~canvas}{empty}
1436 }){}
1437 \__gotham_add_beamerframe_key:n {noBGC}

```

(End of definition for `\begin{frame}[noBCG]`. This function is documented on page ??.)

\l_gotham_defaultWatermark Boolean variable to display the watermark by default (or not).

The following test files are used for this code: gotham-test-038.

```

1438 \bool_new:N \l_gotham_defaultWatermark
1439 \bool_set_false:N \l_gotham_defaultWatermark
1440 % At every new frame, reset the options to default (unless some options/keys are given)
1441 \BeforeBeginEnvironment{frame}{
1442   \bool_if:NTF \l_gotham_defaultWatermark {
1443     \setbeamertemplate{background}{watermark/\prop_item:Nn \l__gotham_template_name_prop {background/watermark}}
1444   }{\% false
1445     \setbeamertemplate{background}{empty}
1446   }
1447 }

```

(End of definition for `\l_gotham_defaultWatermark`. This function is documented on page 29.)

]\begin{frame}[watermark] Add a frame option `watermark` to display an empty background canvas. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-038.

```

1448 % bool to trigger the add of watermark in background
1449 \newenvironment{watermarkenv}{
1450   \setbeamertemplate{background}[
1451     watermark/\prop_item:Nn \l__gotham_template_name_prop {background/watermark}
1452   ]
1453 }){}
1454 \__gotham_add_beamerframe_key:n {watermark}

```

(End of definition for `\begin{frame}[watermark]`. This function is documented on page 29.)

]\begin{frame}[nowatermark] Add a frame option `nowatermark` to do not display an empty background canvas. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-038.

```
1455 % bool to trigger the add of nowatermark in background
```

```

1456 \newenvironment{nowatermarkenv}{
1457   \setbeamertemplate{background}{empty}
1458 }{}
1459 \__gotham_add_beamerframe_key:n {nowatermark}

```

(End of definition for `\begin{frame}[nowatermark]`. This function is documented on page 29.)

```

\l__gotham_tmpa_seq tmp variables
\l__gotham_tmpa_tl
\l__gotham_tmpb_tl
1460 \seq_if_exist:NTF \l__gotham_tmpa_seq
1461 {}{
1462   % sequence
1463   \seq_new:N \l__gotham_tmpa_seq
1464 }
1465 \tl_if_exist:NTF \l__gotham_tmpa_tl
1466 {}{
1467   % token list A
1468   \tl_new:N \l__gotham_tmpa_tl
1469 }
1470 \tl_if_exist:NTF \l__gotham_tmpb_tl
1471 {}{
1472   % token list B
1473   \tl_new:N \l__gotham_tmpb_tl
1474 }

```

(End of definition for `\l__gotham_tmpa_seq`, `\l__gotham_tmpa_tl`, and `\l__gotham_tmpb_tl`.)

__gotham_set_prop_template:nn

#1 : element name (from beamer doc) in other word, the name the template category
#2 : prefined option (from beamer doc)

Function that store in a map the name a template use later. The following naming convention is used: Template/What/Who Name: watermark/gotham draft. This means for example that if a beamer template is defined using `\defbeamertemplate{background}{watermark/gotham}` then the function has to be call using `__gotham_set_prop_template{background/watermark}{gotham}` that will filled internally the map using the l3 command `\prop_put:Nnn \l__gotham_template_name_prop {#1} {#2}`. If the template name given as input does not exist, an error is raised.

The following test files are used for this code: gotham-test-039.

```
1475 \cs_if_exist:NTF \__gotham_set_prop_template:nn {}{  
1476   % if it doesn't exist, then create it.  
1477   \cs_new_protected:Nn \__gotham_set_prop_template:nn  
1478   {  
1479     % Check if the first argument contains a /  
1480     \tl_if_in:nnTF {#1} { / }  
1481     {  
1482       % Split the first around the /  
1483       \seq_set_split:Nnn \l__gotham_tmpa_seq { / } {#1}  
1484       \tl_set:Nn \l__gotham_tmpa_tl { \seq_item:Nn \l__gotham_tmpa_seq { 1 } }  
1485       \tl_set:Nn \l__gotham_tmpb_tl { \seq_item:Nn \l__gotham_tmpa_seq { 2 } }  
1486       % Check if template exist  
1487       \cs_if_exist:cTF {beamer@@tmpop@}\exp_not:V \l__gotham_tmpa_tl @\exp_not:V \l__gotham_tmpb_tl @  
1488       % set the value in the map, so it can be called later.  
1489       \prop_put:Nnn \l__gotham_template_name_prop {#1} {#2}  
1490       % \setbeamertemplate{#1}[#2]  
1491     }{  
1492       \PackageError{beamerthemegotham}{  
1493         The-beamer-template-named-' \l__gotham_tmpa_tl '-with-the-option-' \l__gotham_tmpb_tl / #2 '-  
1494         helping-message}  
1495     }  
1496   }% false -> error  
1497   \PackageError{beamerthemegotham}{  
1498   {  
1499     When-using-' \c_underscore_str \cs_to_str:N \__gotham_set_prop_template '-the-first-argument  
1500     As-example:-if-' \c_underscore_str \defbeamertemplate{background}{watermark/gotham-draft}' .  
1501   }{helping-message}  
1502 }  
1503 }  
1504 }
```

`inner_key_interface` Controls the inner settings for background and watermark).

The following test files are used for this code: gotham-test-037.

```
1505 \keys_define:nn { gotham / inner }{
1506   % watermark template
1507   watermark-template .usage:n = { general },
1508   watermark-template .default:n = { gotham-draft },
1509   watermark-template .code:n = { \__gotham_set_prop_template:nn{background/watermark}{#1} },
1510 }
1511 \keys_define:nn { gotham / inner }{
1512   % watermark default
1513   watermark-default .choice:,
1514   watermark-default .usage:n = { general },
1515   watermark-default .default:n = { false },
1516
1517   watermark-default / true .code:n = { \bool_set_true:N \l_gotham_defaultWatermark },
1518   watermark-default / on .code:n = { \bool_set_true:N \l_gotham_defaultWatermark },
1519   watermark-default / enable .code:n = { \bool_set_true:N \l_gotham_defaultWatermark },
1520
1521   watermark-default / false .code:n = { \bool_set_false:N \l_gotham_defaultWatermark },
1522   watermark-default / off .code:n = { \bool_set_false:N \l_gotham_defaultWatermark },
1523   watermark-default / disable .code:n = { \bool_set_false:N \l_gotham_defaultWatermark },
1524
1525   watermark-default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~unkn
1526 }
```

(End of definition for `inner key - interface`. This function is documented on page ??.)

Stand IN/OUT

`]\begin{frame}[c]` Add a frame option `c` for improved vertically centered text in the frame. By default, Beamer frames offer the `c` option to *almost* vertically center the text, but the placement is a little too high. To fix this, we redefine the `c` option to equalize `\beamer@frametopskip` and `\beamer@framebottomskip`. This solution was suggested by Enrico Gregorio in an answer to [this Stack Exchange question](#).

The following test files are used for this code: gotham-test-039.

```
1527 \define@key{beamerframe}{c}[true]{
1528   \beamer@frametopskip=0pt~plus~1fill\relax
1529   \beamer@framebottomskip=0pt~plus~1fill\relax
1530   \beamer@frametopskipautobreak=0pt~plus~.4\paperheight\relax
1531   \beamer@framebottomskipautobreak=0pt~plus~.6\paperheight\relax
1532   \def\beamer@initfirstlineunskip{}
```

```
1533 }
```

(End of definition for \begin{frame}[c]. This function is documented on page 29.)

\template{background~canvas}{standout/gotham} Definition of the background canvas template used by the standout frame of gotham theme.

The following test files are used for this code: gotham-test-040.

```
1534 \defbeamertemplate{background~canvas}{standout/gotham}{
1535   % copied from beamer default
1536   \ifbeamercolorempty[bg]{standout}{
1537     % if the background standout color is transparent, do nothing.
1538   }{
1539     \usebeamercolor[bg]{standout}\color{bg}
1540     \vrule~width\paperwidth~height\paperheight
1541   }
1542 }
1543 % Add the template to the prop (dictionary) of background template to use according to the s
1544 \prop_put:Nnn \l__gotham_template_name_prop {background~canvas/standout} {gotham}
```

(End of definition for \defbeamertemplate{background~canvas}{standout/gotham}. This function is documented on page ??.)

\defbeamertemplate{standout}{gotham} Definition of the standout template used by the standout frame of gotham theme. This includes background canvas template, fonts and colors.

The following test files are used for this code: gotham-test-040.

```
1545 \defbeamertemplate*{standout}{gotham}{
1546   % \setkeys{beamerframe}{c}
1547   % \setkeys{beamerframe}{noframenumbering}
1548   % \centering
1549
1550   \setbeamertemplate{background~canvas}[standout/\prop_item:Nn \l__gotham_template_name_prop
1551   % \usebeamertemplate{background~canvas}@[standout/gotham]
1552   \usebeamertemplate{background~canvas}{standout}
1553   % if the background color is switched, then change foreground (font) color.
1554   \ifbeamercolorempty[bg]{primary~palette}{
1555     %true : empty background (transparent)
1556     \setbeamercolor{background~canvas}{
1557       use=primary~palette,
1558       bg=primary~palette.fg
1559     }
1560 }
```

```

1561  %false : background not empty (dark or light)
1562  \setbeamercolor{background~canvas}{
1563    use=primary~palette,
1564    bg=primary~palette.bg
1565  }
1566  }
1567  \setbeamercolor{local~structure}{fg=primary~palette.bg}
1568  \usebeamercolor[fg]{primary~palette}
1569 }

```

(End of definition for \defbeamertemplate{standout}{gotham}. This function is documented on page ??.)

-]**\begin{frame}[standout]** Add a frame option **standout** to display the standout frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-040.

```

1570 \newenvironment{standoutenv}{
1571   \usebeamertemplate{standout}
1572 }{}
1573 \__gotham_add_beamerframe_key:n {standout}

```

(End of definition for \begin{frame}[standout]. This function is documented on page 30.)

- template{background~canvas}{standin/gotham}** Definition of the background canvas template used by the standin frame of gotham theme.

The following test files are used for this code: gotham-test-040.

```

1574 \defbeamertemplate{background~canvas}{standin/gotham}{
1575   \ifbeamercolorempty[bg]{standin}{%
1576     % if the background standin color is transparent, do nothing.
1577   }{%
1578     % Uncomment this if-condition to have a 'light' background in 'transparent' color-mode.
1579     \ifbool{transparentBG}{%
1580       % \color{} is not possible so, it is better to do nothing for transparent bg than creating
1581     }{%
1582       \usebeamercolor[bg]{standin}\color{bg}
1583       \vrule~width\paperwidth~height\paperheight
1584     }%
1585   }%
1586 }%
1587 % Add the template to the prop (dictionary) of background template to use according to the s
1588 \prop_put:Nnn \l__gotham_template_name_prop {background~canvas/standin} {gotham}

```

(End of definition for \defbeamertemplate{background~canvas}{standin/gotham}. This function is documented on page ??.)

\defbeamertemplate{standout}{gotham} Definition of the standout template used by the standout frame of gotham theme. This includes background canvas template, fonts and colors.

The following test files are used for this code: gotham-test-040.

```
1589 \defbeamertemplate*{standin}{gotham}{
1590 %
1591 % \setkeys{beamerframe}{c}
1592 % \setkeys{beamerframe}{noframenumbering}
1593 % \centering
1594 \setbeamertemplate{background~canvas}[standin/\prop_item:Nn \l__gotham_template_name_prop {%
1595 % \usebeamertemplate{background~canvas}@[standin/gotham]
1596 \usebeamertemplate{background~canvas}{[standin/gotham]}
1597 %
1598 % Uncomment this if-condition to have a 'light' frametitle in 'transparent' color-mode.
1599 % \ifbeamercolorempty[bg]{normal~text}%
1600 % %true : empty background (transparent)
1601 % \setbeamercolor{frametitle}{%
1602 %   use=normal~text,
1603 %   bg=colorBG,
1604 %   fg=normal~text.fg
1605 % }
1606 % }{
1607 % false
1608 \setbeamercolor{frametitle}{%
1609   use=normal~text,
1610   bg=normal~text.bg,
1611   fg=normal~text.fg
1612 }
1613 %
1614 % \setbeamercolor{frametitle}{%
1615 %   use=normal~text,
1616 %   bg=normal~text.bg,
1617 %   fg=normal~text.fg
1618 %
1619 }
```

(End of definition for \defbeamertemplate{standout}{gotham}. This function is documented on page ??.)

]\begin{frame}[standin] Add a frame option **standin** to display the standin frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch

the end of the frame.

The following test files are used for this code: gotham-test-040.

```
1620 \newenvironment{standinenv}{  
1621   \usebeamertemplate{standin}  
1622 }{}  
1623 \__gotham_add_beamerframe_key:n {standin}
```

(End of definition for \begin{frame}[standin]. This function is documented on page 30.)

inner_key_interface Controls the inner settings for standout and standin.

The following test files are used for this code: gotham-test-037.

```
1624 \keys_define:nn { gotham / inner }  
1625 {  
1626   % standout BG template  
1627   standout-BG-template .usage:n = { general },  
1628   standout-BG-template .default:n = { gotham },  
1629   standout-BG-template .code:n = {  
1630     \__gotham_set_prop_template:nn{background~canvas/standout}{#1}  
1631   },  
1632 }  
1633 \keys_define:nn { gotham / inner }  
1634 {  
1635   % standin BG template  
1636   standin-BG-template .usage:n = { general },  
1637   standin-BG-template .default:n = { gotham },  
1638   standin-BG-template .code:n = {  
1639     \__gotham_set_prop_template:nn{background~canvas/standin}{#1}  
1640   },  
1641 }  
1642 \keys_define:nn { gotham / inner }  
1643 {  
1644   % standout template  
1645   standout-template .usage:n = { general },  
1646   standout-template .default:n = { gotham },  
1647   standout-template .code:n = {  
1648     \__gotham_set_template:nn{standout}{#1}  
1649   },  
1650 }  
1651 \keys_define:nn { gotham / inner }  
1652 {  
1653   % standin template
```

```

1654   standin~template .usage:n = { general },
1655   standin~template .default:n = { gotham },
1656   standin~template .code:n = {
1657     \__gotham_set_template:nn{standin}{#1}
1658   },
1659 }
```

(End of definition for `inner key - interface`. This function is documented on page ??.)

Sections

- `\begin{frame}[part]` Add a frame option `part` to display the part frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-041.

```

1660 \bool_new:N \l_gotham_partframe
1661 \bool_set_false:N \l_gotham_partframe
1662 \define@key{beamerframe}{part}[true]{
1663   \bool_set_true:N \l_gotham_partframe
1664   \begingroup
1665     \usebeamertemplate{part~frame}
1666 }
1667 \apptocmd{\beamer@resetecodes}{%
1668   \bool_if:NTF \l_gotham_partframe {
1669     \endgroup
1670     \bool_set_false:N \l_gotham_partframe
1671   }{}}
1672 }{}{}%
1673 % \define@key{beamerframe}{part}[true]{
1674 %   \thispagestyle{navigation@part}
1675 %
1676 % \def\ps@navigation@part{
1677 %   \usebeamertemplate{part~frame}
1678 %   \nameuse{ps@navigation}
1679 % }
```

(End of definition for `\begin{frame}[part]`. This function is documented on page 30.)

- `\begin{frame}[section]` Add a frame option `section` to display the section frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-041.

```

1680 \bool_new:N \l_gotham_sectionframe
1681 \bool_set_false:N \l_gotham_sectionframe
1682 \define@key{beamerframe}{section}[true]{
1683   \bool_set_true:N \l_gotham_sectionframe
1684   \begingroup
1685     \usebeamertemplate{section~frame}
1686 }
1687 \apptocmd{\beamer@resetecodes}{%
1688   \bool_if:NTF \l_gotham_sectionframe {
1689     \endgroup
1690     \bool_set_false:N \l_gotham_sectionframe
1691   }{}}
1692 }{}}
1693 % \define@key{beamerframe}{section}[true]{
1694 %   \thispagestyle{navigation@section}
1695 %
1696 % \def\ps@navigation@section{%
1697 %   \usebeamertemplate{section~frame}
1698 %   \cnameuse{ps@navigation}
1699 %
1700 }
```

(End of definition for `\begin{frame}[section]`. This function is documented on page 30.)

- `]\begin{frame}[subsection]` Add a frame option `subsection` to display the subsection frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-041.

```

1700 \bool_new:N \l_gotham_subsectionframe
1701 \bool_set_false:N \l_gotham_subsectionframe
1702 \define@key{beamerframe}{subsec}[true]{
1703   \bool_set_true:N \l_gotham_subsectionframe
1704   \begingroup
1705     \usebeamertemplate{subsection~frame}
1706 }
1707 \apptocmd{\beamer@resetecodes}{%
1708   \bool_if:NTF \l_gotham_subsectionframe {
1709     \endgroup
1710     \bool_set_false:N \l_gotham_subsectionframe
1711   }{}}
1712 }{}}
1713 % \define@key{beamerframe}{subsec}[true]{
1714 %   \thispagestyle{navigation@subsec}
```

```

1715 % }
1716 % \def\ps@navigation@subsec{
1717 %   \usebeamertemplate{subsection~frame}
1718 %   \nameuse{ps@navigation}
1719 %

```

(End of definition for `\begin{frame}[subsection]`. This function is documented on page 30.)

- `]\begin{frame}[subsubsection]` Add a frame option `subsubsection` to display the subsubsection frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-041.

```

1720 \bool_new:N \l_gotham_subsubsectionframe
1721 \bool_set_false:N \l_gotham_subsubsectionframe
1722 \define@key{beamerframe}{subsubsection}[true]{
1723   \bool_set_true:N \l_gotham_subsubsectionframe
1724   \begingroup
1725     \usebeamertemplate{subsubsection~frame}
1726   }
1727 \apptocmd{\beamer@resetecodes}{%
1728   \bool_if:NTF \l_gotham_subsubsectionframe {
1729     \endgroup
1730     \bool_set_false:N \l_gotham_subsubsectionframe
1731   }{}}
1732 }{}{}%
1733 % \define@key{beamerframe}{subsubsection}[true]{
1734 %   \thispagestyle{navigation@subsubsection}
1735 %
1736 % \def\ps@navigation@subsubsection{
1737 %   \usebeamertemplate{subsubsection~frame}
1738 %   \nameuse{ps@navigation}
1739 %

```

(End of definition for `\begin{frame}[subsubsection]`. This function is documented on page 30.)

- `\providebool{partContent}` Boolean variable to enable the table of contents of the part, and the command containing `\partContentName` the 'table of contents' title.

```

1740 % repeated from BeamerExtra
1741 \providebool{partContent}
1742 \booltrue{partContent}
1743 \providecommand{\partContentName}{Part-content}

```

(End of definition for \providebool{partContent} and \partContentName. These variables are documented on page ??.)

\providebool{secContent}
 \secContentName Boolean variable to enable the table of contents of the section, and the command containing the 'table of contents' title.

```
1744 \providebool{sectionContent}
1745 \booltrue{sectionContent}
1746 \providecommand{\secContentName}{Section~content}
```

(End of definition for \providebool{secContent} and \secContentName. These variables are documented on page ??.)

\providebool{subsectionContent}
 \subsecContentName Boolean variable to enable the table of contents of the subsection, and the command containing the 'table of contents' title.

```
1747 \providebool{subsectionContent}
1748 \booltrue{subsectionContent}
1749 \providecommand{\subsecContentName}{Subsection~content}
1750 % Subsubsection is not useful (at least up to understanding of the moment) because we do not
```

(End of definition for \providebool{subsectionContent} and \subsecContentName. These variables are documented on page ??.)

\defbeamertemplate{part-title}{gotham}{Definitions of templates controling how will appear the name/title of the parts, sections, subsections and subsubsections.}

The following test files are used for this code: gotham-test-041.

```
1751 \def\partname{\translate{Part}}
1752 \defbeamertemplate*{part-title}{gotham}{
1753   \usebeamercolor[fg]{part-title}
1754   \usebeamertfont{part-title}
1755   \partname \ \insertromanpartnumber
1756   \\\[1.75ex]
1757   \insertpart
1758 }
1759 \defbeamertemplate*{section-title}{gotham}{
1760   \usebeamercolor[fg]{section-title}
1761   \usebeamertfont{section-title}
1762   \insertsectionnumber.~
1763   \insertsectionhead
1764 }
1765 \defbeamertemplate*{subsection-title}{gotham}{
1766   \usebeamercolor[fg]{subsection-title}
```

```

1767 \usebeamerfont{subsection~title}
1768 \insertsectionnumber.\insertsubsectionnumber.~
1769 \insertsubsectionhead
1770 }
1771 \def\subsubsectionname{\translate{Subsubsection}}
1772 \def\insertsubsubsectionnumber{\arabic{subsubsection}}
1773 \def\subsubsectionpage{\usebeamertemplate*{subsubsection~page}}
1774 \defbeamertemplate*{subsubsection~title}{gotham}{
1775 \usebeamercolor[fg]{subsubsection~title}
1776 \usebeamerfont{subsubsection~title}
1777 \insertsectionnumber.\insertsubsectionnumber.\insertsubsubsectionnumber.~
1778 \insertsubsubsectionhead
1779 }

```

(End of definition for \defbeamertemplate{part~title}{gotham}, \defbeamertemplate{section~title}{gotham}, and \defbeamertemplate{subsection~title}{gotham}. These functions are documented on page ??.)

```
\__gotham_inner_disable_partpage:  
\__gotham_inner_enable_partpage:
```

Commands to disable or enable the display of a 'part page' frame at the beginning of every new part. It replaces the `\newcommand{\gotham@disablepartpage}` and `\newcommand{\gotham@enablepartpage}`

The following test files are used for this code: gotham-test-041.

```
1780 \cs_new_protected:Nn \__gotham_inner_disable_partpage:  
1781 {  
1782   \AtBeginPart{  
1783     % intentionally empty  
1784   }  
1785 }  
1786  
1787 \cs_new_protected:Nn \__gotham_inner_enable_partpage:  
1788 {  
1789   \AtBeginPart{  
1790     \ifbeamer@inframe  
1791       \partpage  
1792     \else  
1793       \frame[c, noframenumbering, part]{\partpage}  
1794     \fi  
1795  
1796     \ifbool{partContent}{  
1797       % true  
1798       \begin{frame}[noframenumbering, tocpart]  
1799         \frametitle{\partContentName}  
1800         \tableofcontents[part=\thepart]  
1801       \end{frame}  
1802     }{  
1803       % else empty  
1804     }  
1805   }  
1806 }
```

```
\__gotham_inner_disable_sectionpage:  
\__gotham_inner_enable_sectionpage:
```

Commands to disable or enable the display of a 'section page' frame at the begining of every new section. It replaces the `\newcommand{\gotham@disablesectionpage}` and `\newcommand{\gotham@enablesectionpage}`

The following test files are used for this code: gotham-test-041.

```
1807 \cs_new_protected:Nn \__gotham_inner_disable_sectionpage:  
1808 {  
1809   \AtBeginSection{  
1810     % intentionally empty  
1811   }  
1812 }  
1813  
1814 \cs_new_protected:Nn \__gotham_inner_enable_sectionpage:  
1815 {  
1816   \AtBeginSection{  
1817     \ifbeamer@inframe  
1818       \sectionpage  
1819     \else  
1820       \frame[c, noframenumbering, section]{\sectionpage}  
1821     \fi  
1822  
1823     \ifbool{sectionContent}{  
1824       % true  
1825       \begin{frame}[nofrakenumbering, tocsec]  
1826         \frametitle{\secContentName}  
1827         {\tableofcontents[currentsection, currentsubsection,  
1828           hideothersubsections,  
1829           sectionstyle=show/shaded,  
1830           ]  
1831         }  
1832       \end{frame}  
1833     }{  
1834       % else empty  
1835     }  
1836   }  
1837 }
```

```
\__gotham_inner_disable_subsectionpage:  
\__gotham_inner_enable_subsectionpage:
```

Commands to disable or enable the display of a 'subsection page' frame at the begining of every new subsection. It replaces the `\newcommand{\gotham@disablesubsectionpage}` and `\newcommand{\gotham@enablesubsectionpage}`

The following test files are used for this code: gotham-test-041.

```
1838 \cs_new_protected:Nn \__gotham_inner_disable_subsectionpage:  
1839 {  
1840     \AtBeginSubsection{  
1841         % intentionally empty  
1842     }  
1843 }  
1844  
1845 \cs_new_protected:Nn \__gotham_inner_enable_subsectionpage:  
1846 {  
1847     \AtBeginSubsection{  
1848         \ifbeamer@inframe  
1849             \subsectionpage  
1850         \else  
1851             \frame[c, noframenumbering, subsec]{\subsectionpage}  
1852         \fi  
1853  
1854         \ifbool{subsectionContent}{  
1855             % true  
1856             \begin{frame}[noframenumbering, tocsubsec]  
1857                 \frametitle{\subsecContentName}  
1858                 {\tableofcontents[currentsection, currentsubsection,  
1859                     %currentsubsubsection,  
1860                     hideothersubsections,  
1861                     sectionstyle=show/shaded,  
1862                     subsectionstyle=show/shaded/hide,  
1863                     subsubsectionstyle=show/show/hide,  
1864                 ]  
1865             }  
1866             \end{frame}  
1867         }{  
1868             % else empty  
1869         }  
1870     }  
1871 }
```

```
\__gotham_inner_disable_subsubsectionpage:  
\__gotham_inner_enable_subsubsectionpage:
```

Commands to disable or enable the display of a 'subsubsection page' frame at the begining of every new subsubsection. It replaces the `\newcommand{\gotham@disablesubsubsectionpage}` and `\newcommand{\gotham@enablesubsubsectionpage}`

The following test files are used for this code: gotham-test-041.

```
1872 \cs_new_protected:Nn \__gotham_inner_disable_subsubsectionpage:  
1873 {  
1874     \AtBeginSubsubsection{  
1875         % intentionally empty  
1876     }  
1877 }  
1878  
1879 \cs_new_protected:Nn \__gotham_inner_enable_subsubsectionpage:  
1880 {  
1881     \AtBeginSubsubsection{  
1882         \ifbeamer@inframe  
1883             \subsubsectionpage  
1884         \else  
1885             \frame[c, noframenumbering, subsubsec]{\subsubsectionpage}  
1886         \fi  
1887     }  
1888 }
```

\gothamProgressSectionHeight Variables used to defined the progress bar in section pages.

```
1889 % horizontal size of the bar (used internally and set to |\textwidth|.   
1890 \newlength{\gotham@progressonsectionpage}  
1891 % vertical size of the bar  
1892 \newlength{\gothamProgressSectionHeight}  
1893 \setlength{\gothamProgressSectionHeight}{3pt}
```

(End of definition for \gothamProgressSectionHeight. This variable is documented on page 30.)

\template[progress-bar-in-section-page]{empty} Templates to disable or enable the display of the progress bar in section pages.

The following test files are used for this code: gotham-test-041.

```
1894 \defbeamertemplate{progress~bar~in~section~page}{empty}{  
1895     \vspace{\gothamProgressSectionHeight+1ex}  
1896 }  
1897  
1898 \def\inserttotalframenumber{100}
```

```

1899 \defbeamertemplate{progress-bar-in-section-page}{display}{
1900   \setlength{\gotham@progressonsectionpage}{%
1901     \textwidth * \ratio{\insertframenumber-pt}{\inserttotalframenumber-pt}
1902   }
1903   \begin{tikzpicture}
1904     \fill[bg] (0,0) rectangle (\textwidth, \gothamProgressSectionHeight);
1905     \fill[fg] (0,0) rectangle (\gotham@progressonsectionpage, \gothamProgressSectionHeight);
1906   \end{tikzpicture}
1907 }
```

(End of definition for \defbeamertemplate{progress-bar-in-section-page}{empty} and \defbeamertemplate{progress-bar-in-section-page}{display})

\sectionhoffset length controlling the horizontal offset of the (section title + progress bar) block.

```

1908 \newlength{\sectionhoffset}
1909 \setlength{\sectionhoffset}{0pt}
```

(End of definition for \sectionhoffset. This variable is documented on page 31.)

ion|subsubsection-page}{progressbar/simple} Template of part |section |subsection |subsubsection pages shared by 'progressbar' and 'simple' style. These pages contain what is inside the part |section |subsection |subsubsection frame (without background and frametitle).

The following test files are used for this code: gotham-test-041.

```

1910 \defbeamertemplate{part-page}{progressbar/simple}{
1911   \%frametitle{toto section}
1912   \centering
1913   \hspace*{\sectionhoffset}
1914   \begin{minipage}{22em}
1915     \%raggedright
1916     \centering
1917     \usebeamertemplate*{part-title}\\"[-1ex]
1918     \usebeamertemplate*{progress-bar-in-section-page}
1919     \par
1920   \end{minipage}
1921   \par
1922   \vspace{\baselineskip}
1923 }
1924 \defbeamertemplate{section-page}{progressbar/simple}{
1925   \%frametitle{toto section}
1926   \centering
1927   \hspace*{\sectionhoffset}
1928   \begin{minipage}{22em}
```

```

1929   \raggedright
1930   \usebeamertemplate*{section-title}{\[-1ex]}
1931   \usebeamertemplate*{progressbar-in-section-page}
1932   \par
1933   \end{minipage}
1934   \par
1935   \vspace{\baselineskip}
1936 }
1937 \defbeamertemplate{subsection-page}{progressbar/simple}{
1938   \%frametitle{toto section}
1939   \centering
1940   \hspace*{\sectionhoffset}
1941   \begin{minipage}{22em}
1942   \raggedright
1943   \usebeamertemplate*{section-title}{\[-1ex]}
1944   \usebeamertemplate*{progressbar-in-section-page}
1945   \par
1946   \usebeamertemplate*{subsection-title}
1947   \end{minipage}
1948   \par
1949   \vspace{\baselineskip}
1950 }
1951 \defbeamertemplate{subsubsection-page}{progressbar/simple}{
1952   \%frametitle{toto section}
1953   \centering
1954   \hspace*{\sectionhoffset}
1955   \begin{minipage}{22em}
1956   \raggedright
1957   \usebeamertemplate*{section-title}{\[-1ex]}
1958   \usebeamertemplate*{progressbar-in-section-page}
1959   \par
1960   \usebeamertemplate*{subsection-title}
1961   \par
1962   \usebeamertemplate*{subsubsection-title}
1963   \end{minipage}
1964   \par
1965   \vspace{\baselineskip}
1966 }

```

(End of definition for \defbeamertemplate*{part/section/subsection/subsubsection-page}{progressbar/simple}.
This function is documented on page ??.)

rt|section|subsection|subsubsection/gotham Background canvas template of part |section |subsection |subsubsection pages.

The following test files are used for this code: gotham-test-041.

```
1967 \defbeamertemplate{background~canvas}{part/gotham}{
1968   \ifbeamercolorempty[bg]{normal~text}{}{\color{bg}\vrule width\paperwidth height\paperheight}
1969 }
1970 \defbeamertemplate{background~canvas}{section/gotham}{
1971   \setbeamertemplate{background~canvas}[part/gotham]
1972   \usebeamertemplate{background~canvas}
1973 }
1974 \defbeamertemplate{background~canvas}{subsection/gotham}{
1975   \setbeamertemplate{background~canvas}[part/gotham]
1976   \usebeamertemplate{background~canvas}
1977 }
1978 \defbeamertemplate{background~canvas}{subsubsection/gotham}{
1979   \setbeamertemplate{background~canvas}[part/gotham]
1980   \usebeamertemplate{background~canvas}
1981 }
```

(End of definition for \defbeamertemplate{background~canvas}{part/section/subsection/subsubsection/gotham}.
This function is documented on page ??.)

section|subsubsection-frame}{gotham-simple} Template for part |section |subsection |subsubsection frames with 'gotham simple' style.

The following test files are used for this code: gotham-test-041.

```
1982 \defbeamertemplate{part~frame}{gotham~simple}{
1983   \setbeamertemplate{background~canvas}[part/gotham]
1984   \setbeamercolor{frametitle}{
1985     use={frametitleSection, normal~text},
1986     bg=frametitleSection.fg,
1987     fg=normal~text.fg
1988   }
1989   \setbeamertemplate{progress-bar-in-section-page}[empty]
1990   \setbeamertemplate{part~page}[progressbar/simple]
1991   % \usebeamertemplate*{part~page} activated automatically
1992 }
1993
1994 \defbeamertemplate{section~frame}{gotham~simple}{
1995   \setbeamertemplate{background~canvas}[section/gotham]
1996   \setbeamercolor{frametitle}{
1997     use={frametitleSection, normal~text},
1998     bg=frametitleSection.fg,
1999     fg=normal~text.fg
2000   }
2001   \setbeamertemplate{progress-bar-in-section-page}[empty]
```

```

2002 \setbeamertemplate{section-page}[progressbar/simple]
2003   % \usebeamertemplate*{section-page}% activated automatically
2004 }
2005
2006 \defbeamertemplate{subsection-frame}{gotham-simple}{
2007   \setbeamertemplate{background~canvas}[subsection/gotham]
2008   \setbeamercolor{frametitle}{
2009     use={frametitleSection, normal~text},
2010     bg=frametitleSection.fg,
2011     fg=normal~text.fg
2012   }
2013   \setbeamertemplate{progress-bar-in-section-page}[empty]
2014   \setbeamertemplate{subsection-page}[progressbar/simple]
2015   % \usebeamertemplate*{subsection-page}% activated automatically
2016 }
2017
2018 \defbeamertemplate{subsubsection-frame}{gotham-simple}{
2019   \setbeamertemplate{background~canvas}[subsubsection/gotham]
2020   \setbeamercolor{frametitle}{
2021     use={frametitleSection, normal~text},
2022     bg=frametitleSection.fg,
2023     fg=normal~text.fg
2024   }
2025   \setbeamertemplate{progress-bar-in-section-page}[empty]
2026   \setbeamertemplate{subsubsection-page}[progressbar/simple]
2027   % \usebeamertemplate*{subsubsection-page}% activated automatically
2028 }

```

*(End of definition for \defbeamertemplate{part/section/subsection/subsubsection-frame}{gotham-simple}.
This function is documented on page ??.)*

on|subsubsection-frame}{gotham-progressbar} Template for part |section |subsection |subsubsection frames with 'gotham progressbar' style.

The following test files are used for this code: gotham-test-041.

```

2029 \defbeamertemplate{part-frame}{gotham-progressbar}{
2030   \setbeamertemplate{background~canvas}[part/gotham]
2031   \setbeamercolor{frametitle}{
2032     use={frametitleSection, normal~text},
2033     bg=frametitleSection.fg,
2034     fg=normal~text.fg
2035   }
2036   \setbeamertemplate{progress-bar-in-section-page}[display]
2037   \setbeamertemplate{part-page}[progressbar/simple]

```

```

2038     % \usebeamertemplate*{part~page}%
2039 }
2040
2041 \defbeamertemplate{section~frame}{gotham~progressbar}{
2042   \setbeamertemplate{background~canvas}[section/gotham]
2043   \setbeamercolor{frametitle}{%
2044     use={frametitleSection, normal~text},
2045     bg=frametitleSection.fg,
2046     fg=normal~text.fg
2047   }
2048   \setbeamertemplate{progress~bar~in~section~page}[display]
2049   \setbeamertemplate{section~page}[progressbar/simple]
2050     % \usebeamertemplate*{section~page}%
2051     activated automatically
2051 }
2052
2053 \defbeamertemplate{subsection~frame}{gotham~progressbar}{
2054   \setbeamertemplate{background~canvas}[subsection/gotham]
2055   \setbeamercolor{frametitle}{%
2056     use={frametitleSection, normal~text},
2057     bg=frametitleSection.fg,
2058     fg=normal~text.fg
2059   }
2060   \setbeamertemplate{progress~bar~in~section~page}[display]
2061   \setbeamertemplate{subsection~page}[progressbar/simple]
2062     % \usebeamertemplate*{subsection~page}%
2062     activated automatically
2063 }
2064
2065 \defbeamertemplate{subsubsection~frame}{gotham~progressbar}{
2066   \setbeamertemplate{background~canvas}[subsubsection/gotham]
2067   \setbeamercolor{frametitle}{%
2068     use={frametitleSection, normal~text},
2069     bg=frametitleSection.fg,
2070     fg=normal~text.fg
2071   }
2072   \setbeamertemplate{progress~bar~in~section~page}[display]
2073   \setbeamertemplate{subsubsection~page}[progressbar/simple]
2074     % \usebeamertemplate*{subsubsection~page}%
2074     activated automatically
2075 }

```

(End of definition for \defbeamertemplate{part/section/subsection/subsubsection-frame}{gotham~progressbar}.
This function is documented on page ??.)

e*{progress-bar-in-splitvert}{empty|display} Internal template to display or disable (empty) the progressbar used in 'splitvert' (split vertically) style.

The following test files are used for this code: gotham-test-041.

```
2076 \defbeamertemplate{progress-bar-in-splitvert}{empty}{  
2077   \vspace{-0.5ex}  
2078 }  
2079  
2080 \defbeamertemplate*{progress-bar-in-splitvert}{display}{  
2081   % \nointerlineskip  
2082   \setlength{\gotham@progressonsectionpage}{  
2083     \paperwidth * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}  
2084   }  
2085   \begin{tikzpicture}  
2086     \fill[bg] (0,0) rectangle (\paperwidth, \gothamProgressSectionHeight);  
2087     \fill[fg] (0,0) rectangle (\gotham@progressonsectionpage, \gothamProgressSectionHeight);  
2088   \end{tikzpicture}  
2089 }
```

(End of definition for \defbeamertemplate*{progress-bar-in-splitvert}{empty/display}. This function is documented on page ??.)

~~\page}{gotham_splitvert_progressbar/simple}~~ Templates for part |section |subsection |subsubsection pages that are common for 'gotham splitvert progressbar' and 'gotham splitvert simple' styles (which implies part |section |subsection |subsubsection frames).

The following test files are used for this code: gotham-test-041.

```
2090 % Part page splitvert.  
2091 \defbeamertemplate{part-page}{gotham-splitvert-progressbar/simple}{  
2092   % \frametitle{part!}  
2093   % \IfEmpty{\insertframetitle}{  
2094     \ifx\beamer@frametitle\empty  
2095       \vspace*{-0.05\paperheight}  
2096     \else %}  
2097       \vspace*{-0.165\paperheight}  
2098     \fi %}  
2099   {  
2100     \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}  
2101     \begin{tikzpicture}[overlay, remember picture]  
2102       \fill[color=gotham@@tempColor] (current-page.north-west) rectangle ([shift = {(0, -0.45\paperheight)}]);  
2103     \end{tikzpicture}  
2104   }  
2105  
2106   % \hspace*{\sectionhoffset}  
2107   \begin{minipage}[b][0.45\paperheight]{\textwidth}  
2108     \centering
```

```

2109  \usebeamertemplate*{part~title}
2110  \end{minipage}
2111  \\[-0.1\baselineskip]
2112  \hspace*{-1.0cm}\noindent
2113  \usebeamertemplate*{progress~bar~in~splitvert}
2114
2115  \newline
2116  \begin{minipage}[t][0.5\paperheight]{\textwidth}
2117  % \vspace{0.5\baselineskip}
2118  % \usebeamerfont{subsection~title}
2119  % \usebeamercolor[bg]{frametitle}
2120  % empty
2121  \end{minipage}
2122 }
2123 \defbeamertemplate{part~frame}{gotham~splitvert~progressbar}{
2124  \setbeamertemplate{background~canvas}[part/gotham]
2125  % \setbeamercolor{frametitle}{}
2126  % \setlength{\sectionhoffset}{1cm}
2127  \setbeamercolor{part~title}{use=frametitle, fg=frametitle.fg}
2128  \setbeamertemplate{progress~bar~in~splitvert}[display]
2129  \setbeamertemplate{part~page}[gotham~splitvert~progressbar/simple]
2130  % \usebeamertemplate*{part~page}%
2131  activated automatically
2132 }
2133 \defbeamertemplate{part~frame}{gotham~splitvert~simple}{
2134  \setbeamertemplate{background~canvas}[part/gotham]
2135  % \setbeamercolor{frametitle}{}
2136  % \setlength{\sectionhoffset}{1cm}
2137  \setbeamercolor{part~title}{use=frametitle, fg=frametitle.fg}
2138  \setbeamertemplate{progress~bar~in~splitvert}[empty]
2139  \setbeamertemplate{part~page}[gotham~splitvert~progressbar/simple]
2140  % \usebeamertemplate*{part~page}%
2141  activated automatically
2142 %
2143 \defbeamertemplate{section~page}{gotham~splitvert~progressbar/simple}%
2144 % \frametitle{section!}
2145 % \IfEmpty{\insertframetitle}{%
2146 \ifx\beamer@frametitle\empty
2147 \vspace*{-0.05\paperheight}
2148 \else %}{%
2149 \vspace*{-0.165\paperheight}
2150 \fi %
2151 {

```

```

2152 \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2153 \begin{tikzpicture}[overlay, remember picture]
2154   \fill[color=gotham@@tempColor] (current-page.north-west) rectangle ([shift = {(0, -0.45\paperheight)}]{\textwidth,-0.45\paperheight}) [rounded corners=1mm];
2155 \end{tikzpicture}
2156 }
2157
2158 \hspace*{\sectionhoffset}
2159 \begin{minipage}[b][0.45\paperheight]{\textwidth}
2160   \usebeamertemplate*{section~title}
2161 \end{minipage}
2162 \\[-0.1\baselineskip]
2163 \hspace*{-1.0cm}\noindent
2164 \usebeamertemplate*{progress~bar~in~splitvert}
2165
2166 \newline
2167 \hspace*{\sectionhoffset}
2168 \begin{minipage}[t][0.5\paperheight]{\textwidth}
2169   % \vspace{0.5\baselineskip}
2170   \usebeamertemplate*{subsection~title}
2171   \usebeamercolor[bg]{frametitle}
2172   % empty
2173 \end{minipage}
2174 }
2175 \defbeamertemplate*{section~frame}{gotham~splitvert~progressbar}{
2176   \setbeamertemplate{background~canvas}[section/gotham]
2177   % \setbeamercolor{frametitle}{}
2178   \setlength{\sectionhoffset}{1cm}
2179   \setbeamercolor{section~title}{use=frametitle, fg=frametitle.fg}
2180   \setbeamertemplate{progress~bar~in~splitvert}[display]
2181   \setbeamertemplate{section~page}{gotham~splitvert~progressbar/simple}
2182   % \usebeamertemplate*{section~page}% activated automatically
2183 }
2184 \defbeamertemplate*{section~frame}{gotham~splitvert~simple}{
2185   \setbeamertemplate{background~canvas}[section/gotham]
2186   % \setbeamercolor{frametitle}{}
2187   \setlength{\sectionhoffset}{1cm}
2188   \setbeamercolor{section~title}{use=frametitle, fg=frametitle.fg}
2189   \setbeamertemplate{progress~bar~in~splitvert}[empty]
2190   \setbeamertemplate{section~page}{gotham~splitvert~progressbar/simple}
2191   % \usebeamertemplate*{section~page}% activated automatically
2192 }
2193
2194 % Subsection page splitvert.

```

```

2195 \defbeamertemplate{subsection~page}{gotham~splitvert~progressbar/simple}{
2196   % \frametitle{subsection!}
2197   % \IfEmpty{\insertframetitle}{%
2198     \ifx\beamer@frametitle\empty
2199       \vspace*{-0.05\paperheight}
2200     \else %{
2201       \vspace*{-0.165\paperheight}
2202     \fi %
2203   {
2204     \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2205     \begin{tikzpicture}[overlay, remember picture]
2206       \fill[color=gotham@@tempColor] (current~page.north~west) rectangle ([shift = {(0, -0.45\paperheight)}] current~page.south~west);
2207     \end{tikzpicture}
2208   }
2209
2210   \hspace*{\sectionhoffset}
2211   \begin{minipage}[b][0.45\paperheight]{\textwidth}
2212     \usebeamertemplate*{section~title}
2213   \end{minipage}
2214   \\[-0.1\baselineskip]
2215   \hspace*{-1.0cm}\noindent
2216   \usebeamertemplate*{progress~bar~in~splitvert}
2217
2218   \newline
2219   \hspace*{\sectionhoffset}
2220   \begin{minipage}[t][0.5\paperheight]{\textwidth}
2221     % \vspace{0.5\baselineskip}
2222     \usebeamertemplate{subsection~title}
2223     \usebeamercolor[bg]{frametitle}
2224     \usebeamertemplate*{subsection~title}
2225     % \par
2226     % \vspace{1em}%phantom subsection
2227   \end{minipage}
2228 }
2229 \defbeamertemplate{subsection~frame}{gotham~splitvert~progressbar}{
2230   \setbeamertemplate{background~canvas}{subsection/gotham}
2231   % \setbeamercolor{frametitle}{}
2232   \setlength{\sectionhoffset}{1cm}
2233   \setbeamercolor{section~title}{use=frametitle, fg=frametitle.fg}
2234   \setbeamercolor{subsection~title}{use=frametitle, fg=frametitle.bg}
2235   \setbeamertemplate{progress~bar~in~splitvert}{display}
2236   \setbeamertemplate{subsection~page}{gotham~splitvert~progressbar/simple}
2237   % \usebeamertemplate*{subsection~page}%

```

```

2238 }
2239 \defbeamertemplate{subsection-frame}{gotham-splitvert-simple}{
2240   \setbeamertemplate{background-canvas}[subsection/gotham]
2241   % \setbeamercolor{frametitle}{}
2242   \setlength{\sectionhoffset}{1cm}
2243   \setbeamercolor{section-title}{use=frametitle, fg=frametitle.fg}
2244   \setbeamercolor{subsection-title}{use=frametitle, fg=frametitle.bg}
2245   \setbeamertemplate{progress-bar-in-splitvert}[empty]
2246   \setbeamertemplate{subsection-page}[gotham-splitvert-progressbar/simple]
2247   % \usebeamertemplate*[subsection-page]{% activated automatically
2248 }
2249
2250 % Subsubsection page splitvert.
2251 \defbeamertemplate{subsubsection-page}{gotham-splitvert-progressbar/simple}{
2252   % \frametitle{subsubsection!}
2253   % \IfEmpty{\insertframetitle}{%
2254     \ifx\beamer@frametitle\@empty
2255       \vspace*{-0.05\paperheight}
2256     \else %\fi
2257       \vspace*{-0.165\paperheight}
2258     \fi
2259   }
2260   \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2261   \begin{tikzpicture}[overlay, remember-picture]
2262     \fill[color=gotham@@tempColor] (current-page.north-west) rectangle ([shift = {(0, -0.45\paperheight)}];
2263   \end{tikzpicture}
2264 }
2265
2266 \hspace*{\sectionhoffset}
2267 \begin{minipage}[b][0.45\paperheight]{\textwidth}
2268   \usebeamertemplate*[section-title]
2269 \end{minipage}
2270 \\[-0.1\baselineskip]
2271 \hspace*{-1.0cm}\noindent
2272 \usebeamertemplate*[progress-bar-in-splitvert]
2273
2274 \newline
2275 \hspace*{\sectionhoffset}
2276 \begin{minipage}[t][0.5\paperheight]{\textwidth}
2277   % \vspace{0.5\baselineskip}
2278   \usebeamertemplate{subsubsection-title}
2279   \usebeamercolor[bg]{frametitle}
2280   \usebeamertemplate*[subsection-title]

```

```

2281   \par
2282   \usebeamertemplate*{subsubsection~title}
2283   \end{minipage}
2284 }
2285 \defbeamertemplate{subsubsection~frame}{gotham-splitvert-progressbar}{
2286   \setbeamertemplate{background~canvas}[subsubsection/gotham]
2287   % \setbeamercolor{frametitle}{}
2288   \setlength{\sectionhoffset}{1cm}
2289   \setbeamercolor{section~title}{use=frametitle, fg=frametitle.fg}
2290   \setbeamercolor{subsection~title}{use=frametitle, fg=frametitle.bg}
2291   \setbeamercolor{subsubsection~title}{use=frametitle, fg=frametitle.bg}
2292   \setbeamertemplate{progress~bar~in~splitvert}[display]
2293   \setbeamertemplate{subsubsection~page}[gotham-splitvert-progressbar/simple]
2294   % \usebeamertemplate*{subsubsection~page}% activated automatically
2295 }
2296 \defbeamertemplate{subsubsection~frame}{gotham-splitvert-simple}{
2297   \setbeamertemplate{background~canvas}[subsubsection/gotham]
2298   % \setbeamercolor{frametitle}{}
2299   \setlength{\sectionhoffset}{1cm}
2300   \setbeamercolor{section~title}{use=frametitle, fg=frametitle.fg}
2301   \setbeamercolor{subsection~title}{use=frametitle, fg=frametitle.bg}
2302   \setbeamercolor{subsubsection~title}{use=frametitle, fg=frametitle.bg}
2303   \setbeamertemplate{progress~bar~in~splitvert}[empty]
2304   \setbeamertemplate{subsubsection~page}[gotham-splitvert-progressbar/simple]
2305   % \usebeamertemplate*{subsubsection~page}% activated automatically
2306 }

```

(End of definition for \defbeamertemplate{part/section/subsection/subsubsection page}{gotham splitvert progressbar/simple}, \defbeamertemplate{part/section/subsection/subsubsection frame}{gotham splitvert progressbar}, and \defbeamertemplate{part/section/subsection/subsubsection frame}{gotham splitvert simple}. These functions are documented on page ??.)

on|subsubsection|page}{gotham|progressvert}
 n|subsubsection|frame}{gotham|progressvert}

Templates for part |section |subsection |subsubsection pages for 'gotham progressvert'.
The following test files are used for this code: gotham-test-041.

```

2307
2308 % Part page progressvert.
2309 \defbeamertemplate{part~page}{gotham-progressvert}{
2310   % \frametitle{part!}
2311   % \IfEmpty{\insertframetitle}{%
2312   %   \ifx\beamer@frametitle\empty
2313   %     \vspace*{-0.05\paperheight}
2314   %   \else %
2315   %     \vspace*{-0.165\paperheight}

```

```

2316 \fi %}
2317 \setlength{\gotham@progressonsectionpage}{%
2318   \paperheight * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}
2319 }
2320 {
2321   \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2322   \colorlet{gotham@@tempColorB}{fg}
2323   \begin{tikzpicture}[overlay, remember picture]
2324     \fill[color=gotham@@tempColor]
2325       ([shift={(0,0)}] current-page.north-west) --
2326       ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-west) --
2327       ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-east) --
2328       ([shift={(0,0)}] current-page.north-east)
2329     --cycle;
2330   \node[color=gotham@@tempColorB, align=left, text-width=0.8\textwidth] at ([shift={(\sectionwidth,0)}])
2331     {\usebeamertemplate{part-title}}
2332     \partname \ \insertromanpartnumber
2333     \\[1.75ex]
2334     \insertpart
2335   }
2336 };
2337
2338 \clip
2339   ([shift={(0,0)}] current-page.south-west) --
2340   ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2341   ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2342   ([shift={(0,0)}] current-page.south-east)
2343 --cycle;
2344
2345 \fill[color=gotham@@tempColorB]
2346   ([shift={(0,0)}] current-page.south-west) --
2347   ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2348   ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2349   ([shift={(0,0)}] current-page.south-east)
2350 --cycle;
2351 \node[color=gotham@@tempColor, align=left, text-width=0.8\textwidth] at ([shift={(\sectionwidth,0)}])
2352   {\usebeamertemplate{part-title}}
2353   \partname \ \insertromanpartnumber
2354   \\
2355   \insertpart
2356 }
2357 };
2358 \end{tikzpicture}

```

```

2359 }
2360 }
2361 \defbeamertemplate{part~frame}{gotham-progressvert}{
2362   \setbeamertemplate{background~canvas}[part/gotham]
2363   % \setbeamercolor{frametitle}{}
2364   \setlength{\sectionhoffset}{1cm}
2365   % \setbeamercolor{section~title}{use=frametitle, fg=frametitle.bg}
2366   % \setbeamercolor{subsection~title}{use=frametitle, fg=frametitle.bg}
2367   % \setbeamercolor{part~title}{use=frametitle, fg=frametitle.bg}
2368   % \setbeamertemplate{progress~bar~in~splitvert}[display]
2369   \setbeamertemplate{part~page}[gotham-progressvert]
2370   % \usebeamertemplate*{section~page}% activated automatically
2371 }
2372
2373 % Section page progressvert.
2374 \defbeamertemplate{section-page}{gotham-progressvert}{
2375   % \frametitle{section!}
2376   % \IfEmpty{\insertframetitle}{%
2377     \ifx\beamer@frametitle\empty
2378       \vspace*{-0.05\paperheight}
2379     \else %{
2380       \vspace*{-0.165\paperheight}
2381     \fi %}
2382   \setlength{\gotham@progressonsectionpage}{%
2383     \paperheight * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}
2384   }
2385   {
2386     \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2387     \colorlet{gotham@@tempColorB}{fg}
2388     \begin{tikzpicture}[overlay, remember picture]
2389       \fill[color=gotham@@tempColor]
2390         ([shift={(0,0)}] current-page.north-west) --
2391         ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-west) --
2392         ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-east) --
2393         ([shift={(0,0)}] current-page.north-east)
2394       --cycle;
2395     \node[color=gotham@@tempColorB, align=left, text-width=0.8\textwidth] at ([shift={(\sectionhoffset, -\gotham@progressonsectionpage)}] current-page.north) {
2396       \usebeamertemplate{section~title}
2397       \insertsectionnumber.~
2398       \insertsectionhead
2399     };
2400   \clip

```

```

2402     ([shift={(0,0)}] current-page.south-west) --
2403     ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2404     ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2405     ([shift={(0,0)}] current-page.south-east)
2406     --cycle;
2407
2408 \fill[color=gotham@@tempColorB]
2409   ([shift={(0,0)}]current-page.south-west) --
2410   ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2411   ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2412   ([shift={(0,0)}] current-page.south-east)
2413   --cycle;
2414 \node[color=gotham@@tempColor, align=left, text-width=0.8\textwidth] at ([shift={(\sectionoffset,0)}]
2415   {\usebeamertemplate{section-title}}
2416   \insertsectionnumber.~
2417   \insertsectionhead}
2418   {};
2419 \end{tikzpicture}
2420 }
2421 }
2422 \defbeamertemplate{section-frame}{gotham-progressvert}{
2423   \setbeamertemplate{background-canvas}[section/gotham]
2424   % \setbeamercolor{frametitle}{}
2425   \setlength{\sectionhoffset}{1cm}
2426   % \setbeamercolor{section-title}{use=frametitle, fg=frametitle.bg}
2427   % \setbeamercolor{subsection-title}{use=frametitle, fg=frametitle.bg}
2428   % \setbeamercolor{section-title}{use=frametitle, fg=frametitle.bg}
2429   % \setbeamertemplate{progress-bar-in-splitvert}[display]
2430   \setbeamertemplate{section-page}[gotham-progressvert]
2431   % \usebeamertemplate*{section-page}% activated automatically
2432 }
2433
2434 % Subection page progressvert.
2435 \defbeamertemplate{subsection-page}{gotham-progressvert}{
2436   % \frametitle{subsection!}
2437   % \IfEmpty{\insertframetitle}{%
2438   \ifx\beamer@frametitle\empty
2439     \vspace*{-0.05\paperheight}
2440   \else %
2441     \vspace*{-0.165\paperheight}
2442   \fi %
2443   \setlength{\gotham@progressonsectionpage}{%
2444     \paperheight * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}

```

```

2445 }
2446 {
2447 \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2448 \colorlet{gotham@@tempColorB}{fg}
2449 \begin{tikzpicture}[overlay, remember picture]
2450 \fill[color=gotham@@tempColor]
2451 ([shift={(0,0)}] current-page.north-west) --
2452 ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-west) --
2453 ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-east) --
2454 ([shift={(0,0)}] current-page.north-east)
2455 --cycle;
2456 \node[color=gotham@@tempColorB, align=left, text-width=0.8\textwidth] at ([shift={(\sectiontitlewidth,0)}])
2457 {\usebeamertfont{section-title}}
2458 \insertsectionnumber.~
2459 \insertsectionhead}
2460 \\
2461 {\usebeamertfont{subsection-title}}
2462 \insertsectionnumber.\insertsubsectionnumber.~
2463 \insertsubsectionhead}
2464 };
2465
2466 \clip
2467 ([shift={(0,0)}] current-page.south-west) --
2468 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2469 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2470 ([shift={(0,0)}] current-page.south-east)
2471 --cycle;
2472
2473 \fill[color=gotham@@tempColorB]
2474 ([shift={(0,0)}] current-page.south-west) --
2475 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2476 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2477 ([shift={(0,0)}] current-page.south-east)
2478 --cycle;
2479 \node[color=gotham@@tempColor, align=left, text-width=0.8\textwidth] at ([shift={(\subsectiontitlewidth,0)}])
2480 {\usebeamertfont{section-title}}
2481 \insertsectionnumber.~
2482 \insertsectionhead}
2483 \\
2484 {\usebeamertfont{subsection-title}}
2485 \insertsectionnumber.\insertsubsectionnumber.~
2486 \insertsubsectionhead}
2487 };

```

```

2488     \end{tikzpicture}
2489 }
2490 }
2491 \defbeamertemplate{subsection-frame}{gotham-progressvert}{
2492     \setbeamertemplate{background-canvas}[subsection/gotham]
2493     % \setbeamercolor{frametitle}{}
2494     \setlength{\sectionhoffset}{1cm}
2495     % \setbeamercolor{section-title}{use=frametitle, fg=frametitle.bg}
2496     % \setbeamercolor{subsection-title}{use=frametitle, fg=frametitle.bg}
2497     % \setbeamercolor{subsection-title}{use=frametitle, fg=frametitle.bg}
2498     % \setbeamertemplate{progress-bar-in-splitvert}[display]
2499     \setbeamertemplate{subsection-page}[gotham-progressvert]
2500     % \usebeamertemplate*{subsection-page}% activated automatically
2501 }
2502
2503 % Subsubsection page progressvert.
2504 \defbeamertemplate{subsubsection-page}{gotham-progressvert}{
2505     % \frametitle{subsubsection!}
2506     % \IfEmpty{\insertframetitle}{%
2507     \ifx\beamer@frametitle\empty
2508         \vspace*{-0.05\paperheight}
2509     \else %}%
2510         \vspace*{-0.165\paperheight}
2511     \fi %}
2512     \setlength{\gotham@progressonsectionpage}{%
2513         \paperheight * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}
2514     }
2515     {
2516         \usebeamercolor{frametitle}\colorlet{gotham@@tempColor}{bg}
2517         \colorlet{gotham@@tempColorB}{fg}
2518         \begin{tikzpicture}[overlay, remember-picture]
2519             \fill[color=gotham@@tempColor]
2520                 ([shift={(0,0)}] current-page.north-west) --
2521                 ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-west) --
2522                 ([shift={(0,-\gotham@progressonsectionpage)}] current-page.north-east) --
2523                 ([shift={(0,0)}] current-page.north-east)
2524             --cycle;
2525             \node[color=gotham@@tempColorB, align=left, text-width=0.8\textwidth] at ([shift={(\sectionhoffset, -\gotham@progressonsectionpage)}])
2526                 {\usebeamercolor{section-title}}
2527                 \insertsectionnumber.~
2528                 \insertsectionhead
2529                 \\
2530                 \usebeamercolor{subsection-title}}

```

```

2531   \insertsectionnumber.\insertsubsectionnumber.~
2532   \insertsubsectionhead}
2533   \\
2534   {\usebeamertemplate{subsubsection~title}}
2535   \insertsectionnumber.\insertsubsectionnumber.\insertsubsubsectionnumber.~
2536   \insertsubsubsectionhead}
2537 };
2538
2539 \clip
2540 ([shift={(0,0)}] current-page.south-west) --
2541 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2542 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2543 ([shift={(0,0)}] current-page.south-east)
2544 --cycle;
2545
2546 \fill [color=gotham@@tempColorB]
2547 ([shift={(0,0)}]current-page.south-west) --
2548 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-west) --
2549 ([shift={(0,\paperheight-\gotham@progressonsectionpage)}] current-page.south-east) --
2550 ([shift={(0,0)}] current-page.south-east)
2551 --cycle;
2552 \node [color=gotham@@tempColor, align=left, text-width=0.8\textwidth] at ([shift={(\sectionwidth-\frametitlewidth)/2,0}])
2553 {\usebeamertemplate{section~title}}
2554 \insertsectionnumber.~
2555 \insertsectionhead}
2556 \\
2557 {\usebeamertemplate{subsection~title}}
2558 \insertsectionnumber.\insertsubsectionnumber.~
2559 \insertsubsectionhead}
2560 \\
2561 {\usebeamertemplate{subsubsection~title}}
2562 \insertsectionnumber.\insertsubsectionnumber.\insertsubsubsectionnumber.~
2563 \insertsubsubsectionhead}
2564 };
2565 \end{tikzpicture}
2566 }
2567 }
2568 \defbeamertemplate{subsubsection~frame}{gotham-progressvert}{%
2569   \setbeamertemplate{background~canvas}[subsubsection/gotham]
2570   % \setbeamercolor{frametitle}{}
2571   \setlength{\sectionhoffset}{1cm}
2572   % \setbeamercolor{section~title}{use=frametitle, fg=frametitle.bg}
2573   % \setbeamercolor{subsection~title}{use=frametitle, fg=frametitle.bg}

```

```

2574 % \setbeamercolor{subsubsection~title}{use=frametitle, fg=frametitle.bg}
2575 % \setbeamertemplate{progress-bar-in-splitvert}[display]
2576 \setbeamertemplate{subsubsection~page}[gotham-progressvert]
2577 % \usebeamertemplate*{subsubsection~page}% activated automatically
2578 }

```

(End of definition for \defbeamertemplate{part/section/subsection/subsubsection page}{gotham progressvert} and \defbeamertemplate{part/section/subsection/subsubsection frame}{gotham progressvert}. These functions are documented on page ??.)

- `inner_key_interface` Controls the inner settings for partframe (or `sectionframe`, `subsectionframe` and `subsubsectionframe` respectively) and standin.

The following test files are used for this code: `gotham-test-041`.

```

2579 \keys_define:nn { gotham / inner }{
2580   % partframe template
2581   partframe~template .usage:n = { general },
2582   partframe~template .default:n = { gotham-progressbar },
2583   partframe~template .code:n = { \__gotham_set_template:nn{part~frame}{#1} }
2584 }
2585 \keys_define:nn { gotham / inner }{
2586   % partframe default
2587   partframe~default .choice:,
2588   partframe~default .usage:n = { general },
2589   partframe~default .default:n = { true },
2590
2591   partframe~default / true .code:n = { \__gotham_inner_enable_partpage: },
2592   partframe~default / on .code:n = { \__gotham_inner_enable_partpage: },
2593   partframe~default / enable .code:n = { \__gotham_inner_enable_partpage: },
2594
2595   partframe~default / false .code:n = { \__gotham_inner_disable_partpage: },
2596   partframe~default / off .code:n = { \__gotham_inner_disable_partpage: },
2597   partframe~default / disable .code:n = { \__gotham_inner_disable_partpage: },
2598
2599
2600   partframe~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~unknown } }
2601 }
2602
2603 \keys_define:nn { gotham / inner }{
2604   % sectionframe template
2605   sectionframe~template .usage:n = { general },
2606   sectionframe~template .default:n = { gotham-progressbar },
2607   sectionframe~template .code:n = { \__gotham_set_template:nn{section~frame}{#1} }
2608 }

```

```

2609 \keys_define:nn { gotham / inner }
2610 {
2611   % sectionframe default
2612   sectionframe~default .choice:,
2613   sectionframe~default .usage:n = { general },
2614   sectionframe~default .default:n = { true },
2615
2616   sectionframe~default / true .code:n = { \__gotham_inner_enable_sectionpage: },
2617   sectionframe~default / on .code:n = { \__gotham_inner_enable_sectionpage: },
2618   sectionframe~default / enable .code:n = { \__gotham_inner_enable_sectionpage: },
2619
2620   sectionframe~default / false .code:n = { \__gotham_inner_disable_sectionpage: },
2621   sectionframe~default / off .code:n = { \__gotham_inner_disable_sectionpage: },
2622   sectionframe~default / disable .code:n = { \__gotham_inner_disable_sectionpage: },
2623
2624   sectionframe~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u~}
2625 }
2626
2627 \keys_define:nn { gotham / inner }{
2628   % subsectionframe template
2629   subsectionframe~template .usage:n = { general },
2630   subsectionframe~template .default:n = { gotham~progressbar },
2631   subsectionframe~template .code:n = { \__gotham_set_template:nn{subsection~frame}{#1} }
2632 }
2633 \keys_define:nn { gotham / inner }
2634 {
2635   % subsectionframe default
2636   subsectionframe~default .choice:,
2637   subsectionframe~default .usage:n = { general },
2638   subsectionframe~default .default:n = { true },
2639
2640   subsectionframe~default / true .code:n = { \__gotham_inner_enable_subsectionpage: },
2641   subsectionframe~default / on .code:n = { \__gotham_inner_enable_subsectionpage: },
2642   subsectionframe~default / enable .code:n = { \__gotham_inner_enable_subsectionpage: },
2643
2644   subsectionframe~default / false .code:n = { \__gotham_inner_disable_subsectionpage: },
2645   subsectionframe~default / off .code:n = { \__gotham_inner_disable_subsectionpage: },
2646   subsectionframe~default / disable .code:n = { \__gotham_inner_disable_subsectionpage: },
2647
2648   subsectionframe~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u~}
2649 }
2650
2651 \keys_define:nn { gotham / inner }{

```

```

2652 % subsubsectionframe template
2653 subsubsectionframe-template .usage:n = { general },
2654 subsubsectionframe-template .default:n = { gotham~progressbar },
2655 subsubsectionframe-template .code:n = { \__gotham_set_template:nn{subsubsection-frame}{#1}
2656 }
2657 \keys_define:nn { gotham / inner }
2658 {
2659   % subsubsectionframe default
2660   subsubsectionframe-default .choice:,
2661   subsubsectionframe-default .usage:n = { general },
2662   subsubsectionframe-default .default:n = { true },
2663
2664   subsubsectionframe-default / true .code:n = { \__gotham_inner_enable_subsubsectionpage: },
2665   subsubsectionframe-default / on .code:n = { \__gotham_inner_enable_subsubsectionpage: },
2666   subsubsectionframe-default / enable .code:n = { \__gotham_inner_enable_subsubsectionpage: },
2667
2668   subsubsectionframe-default / false .code:n = { \__gotham_inner_disable_subsubsectionpage: },
2669   subsubsectionframe-default / off .code:n = { \__gotham_inner_disable_subsubsectionpage: },
2670   subsubsectionframe-default / disable .code:n = { \__gotham_inner_disable_subsubsectionpage: },
2671
2672   subsubsectionframe-default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'##1
2673 } }
```

(End of definition for `inner` key - interface. This function is documented on page ??.)

Table of Content

\tikzset{section-number/.style={}} Definition of how sections, subsections and subsubsections' numbers will appear in 'gotham bullet' style for tables of contents.

The following test files are used for this code: gotham-test-042.

```

2674 \tikzset{section-number/.style={
2675   circle,
2676   fill=colorAlert,
2677   minimum-size=0.4em,
2678   text=colorAlert!10,
2679   inner-sep=1.5pt,
2680 },
2681 section/.style={
2682   draw=none,
2683   rectangle,
2684   minimum-height=1em,
2685   minimum-width=0.8\textwidth,
2686   text-width=0.8\textwidth,
```

```

2687   text=fg,
2688   align=left
2689 },
2690 subsection~number/.style={
2691   circle,
2692   fill=colorBackElement!50,
2693   inner sep=0pt,
2694   minimum size=0.15cm,
2695 },
2696 subsection/.style={
2697   draw=none,
2698   rectangle,
2699   minimum height=1em,
2700   minimum width=0.8\textwidth,
2701   text width=0.8\textwidth,
2702   text=fg!80,
2703   align=left
2704 },
2705 subsubsection~number/.style={
2706   circle,
2707   fill=colorBackElement!50,
2708   inner sep=0pt,
2709   minimum size=0.06cm,
2710 },
2711 subsubsection/.style={
2712   draw=none,
2713   rectangle,
2714   minimum height=1em,
2715   minimum width=0.8\textwidth,
2716   text width=0.8\textwidth,
2717   text=fg!80,
2718   align=left
2719 },
2720 }

```

(End of definition for \tikzset{section~number/.style={}}. This function is documented on page ??.)

Template definitions for gotham bullet style of ToC that appear in section |subsection |subsubsection frame.

The following test files are used for this code: gotham-test-042.

```

2721 \defbeamertemplate{section-in-toc}{gotham-bullet}{
2722   \hspace*{0.4cm}\tikz[baseline=-0.5ex]\node[section-number]{\textbf{\small\inserttocsectionn}

```

```

2723   \tikz [baseline=-0.5ex] \node [section] {\usebeamertemplate{toc~title} \insertttocsection}; \\[-0.5ex]
2724   \hspace*{1.13cm}{\usebeamercolor*[fg]{footer} \rule{0.6\paperwidth}{0.2pt} \\ \nointerlineskip}
2725 }
2726 \defbeamertemplate{subsection~in~toc}{gotham~bullet}{
2727   \hspace*{0.53cm}\tikz [baseline=-0.5ex] \node [subsection~number] {};
2728   \hspace*{0.5cm}\tikz [baseline=-0.5ex] \node [subsection] {\usebeamertemplate{toc~subtitle}\insertttocsubsection};
2729 }
2730 \defbeamertemplate{subsubsection~in~toc}{gotham~bullet}{
2731   \hspace*{0.58cm}\tikz [baseline=-0.5ex] \node [subsubsection~number] {};
2732   \hspace*{0.69cm}\tikz [baseline=-0.5ex] \node [subsubsection] {\usebeamertemplate{toc~subtitle}\insertttocsubsubsection};
2733 }
2734 % Shaded for sections already done in the presentation.
2735 \defbeamertemplate{section~in~toc~shaded}{gotham~bullet}{
2736   \hspace*{0.4cm}\tikz [baseline=-0.5ex] \node [section~number, fill=colorBackElement!40, text=black];
2737   \tikz [baseline=-0.5ex] \node [section, text=colorExample!20] {\usebeamertemplate{toc~title} \insertttocsection};
2738   \hspace*{1.3cm}{\usebeamercolor*[fg]{footer} \rule{0.6\paperwidth}{0.2pt} \\ \nointerlineskip};
2739 }
2740 \defbeamertemplate{subsection~in~toc~shaded}{gotham~bullet}{
2741   \hspace*{0.55cm}\tikz [baseline=-0.5ex] \node [subsection~number,fill=colorBackElement!20]{};
2742   \hspace*{0.5cm}\tikz [baseline=-0.5ex] \node [subsection, text=colorBackElement!20]{}; \\[-0.2cm];
2743 }
2744 \defbeamertemplate{subsubsection~in~toc~shaded}{gotham~bullet}{
2745   \hspace*{0.58cm}\tikz [baseline=-0.5ex] \node [subsubsection~number,fill=colorBackElement!20]{};
2746   \hspace*{0.69cm}\tikz [baseline=-0.5ex] \node [subsubsection, text=colorBackElement!20] {\usebeamertemplate{toc~subtitle}\insertttocsubsubsection};
2747 }

```

(End of definition for \defbeamertemplate{section~in~toc}{gotham~bullet}. This function is documented on page ??.)

amertemplate{section~in~toc}{gotham~bullet}

Template definitions for gotham simple style of ToC that appear in section | subsection | subsubsection frame.

The following test files are used for this code: gotham-test-042.

```

2748 \defbeamertemplate{part~in~toc}{gotham~simple} {
2749   {\insertttocpartnumber} . } ~ \insertttocpart
2750   \\
2751 }
2752 \defbeamertemplate{section~in~toc}{gotham~simple} {
2753   {\insertttocsectionnumber} . } ~ \insertttocsection
2754   \\
2755 }
2756 \defbeamertemplate{subsection~in~toc}{gotham~simple} {
2757   \quad {\insertttocsectionnumber} . \insertttocsubsectionnumber . } ~ \insertttocsubsection
2758   \\

```

```

2759 }
2760 \defbeamertemplate{subsubsection-in-toc}{gotham-simple}{
2761   \quad\quad{\inserttocsectionnumber}.\inserttocsubsectionnumber.\inserttocsubsubsectionnumber.}
2762   \\
2763 }

```

(End of definition for \defbeamertemplate{section-in-toc}{gotham-bullet}. This function is documented on page ??.)

plate{background-canvas}{toc/gotham-simple} Definition of toc page style named gotham simple and gotham bullet, used for table of content pages. Both are using a dedicated background canvas.

The following test files are used for this code: gotham-test-042.

```

2764 \defbeamertemplate{background-canvas}{toc/gotham-simple}{
2765   \ifbeamercolorempty[bg]{standin}{}{
2766     \color{bg}\vrule width\paperwidth height\paperheight
2767   }
2768 }
2769 \defbeamertemplate{toc-page}{gotham-simple}{
2770   \setbeamertemplate{part-in-toc}[gotham-simple]
2771   \setbeamertemplate{section-in-toc}[gotham-simple]
2772   \setbeamertemplate{subsection-in-toc}[gotham-simple]
2773   \setbeamertemplate{subsubsection-in-toc}[gotham-simple]
2774   \setbeamertemplate{background-canvas}[toc/gotham-simple]
2775 }
2776 \defbeamertemplate{toc-page}{gotham-bullet}{
2777   \setbeamertemplate{part-in-toc}[gotham-bullet]
2778   \setbeamertemplate{section-in-toc}[gotham-bullet]
2779   \setbeamertemplate{subsection-in-toc}[gotham-bullet]
2780   \setbeamertemplate{subsubsection-in-toc}[gotham-bullet]
2781   \setbeamertemplate{background-canvas}[toc/gotham-simple]
2782 }

```

(End of definition for \defbeamertemplate{background-canvas}{toc/gotham-simple} and \defbeamertemplate{toc-page}. These functions are documented on page ??.)

]\begin{frame}[toc] Add a frame option `toc` to display the toc frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-042.

```

2783 \newenvironment{tocenv}{
2784   \usebeamertemplate{toc-page}

```

```

2785 }){}
2786 \__gotham_add_beamerframe_key:n {toc}

```

(End of definition for `\begin{frame}[toc]`. This function is documented on page 31.)

`canvas}{toc-part|section|subsection-gotham}` Definition of the background canvas used by the toc in part | section | subsection.

The following test files are used for this code: gotham-test-042.

```

2787 \defbeamertemplate{background~canvas}{toc~part~gotham}{
2788   \ifbeamercolorempty[bg]{normal~text}{}{\color{bg}\vrule width\paperwidth height\paperheight}
2789 }
2790 \defbeamertemplate{background~canvas}{toc~section~gotham}{
2791   \ifbeamercolorempty[bg]{normal~text}{}{\color{bg}\vrule width\paperwidth height\paperheight}
2792 }
2793 \defbeamertemplate{background~canvas}{toc~subsection~gotham}{
2794   \ifbeamercolorempty[bg]{normal~text}{}{\color{bg}\vrule width\paperwidth height\paperheight}
2795 }

```

(End of definition for `\defbeamertemplate{background~canvas}{toc~part~section~subsection-gotham}`. This function is documented on page ??.)

`amertemplate{toc-part-frame}{gotham-simple}` Definition of the toc in part | section | subsection templates for gotham simple style.

The following test files are used for this code: gotham-test-042.

```

2796 \defbeamertemplate{toc~part~frame}{gotham~simple}{
2797   \setbeamertemplate{part~in~toc}[gotham~simple]
2798   \setbeamertemplate{section~in~toc}[gotham~simple]
2799   \setbeamertemplate{subsection~in~toc}[gotham~simple]
2800   \setbeamertemplate{subsubsection~in~toc}[gotham~simple]
2801   \setbeamertemplate{background~canvas}[toc~part~gotham]
2802   \setbeamertemplate{frametitle}[toc~gotham]
2803   % \usebeamertemplate*{part~page}% already included
2804 }
2805 \defbeamertemplate{toc~section~frame}{gotham~simple}{
2806   \setbeamertemplate{part~in~toc}[gotham~simple]
2807   \setbeamertemplate{section~in~toc}[gotham~simple]
2808   \setbeamertemplate{subsection~in~toc}[gotham~simple]
2809   \setbeamertemplate{subsubsection~in~toc}[gotham~simple]
2810   \setbeamertemplate{background~canvas}[toc~section~gotham]
2811   \setbeamertemplate{frametitle}[toc~gotham]%
2812   % \usebeamertemplate*{section~page}% already included
2813 }
2814 \defbeamertemplate{toc~subsection~frame}{gotham~simple}{
2815   \setbeamertemplate{part~in~toc}[gotham~simple]

```

```

2816 \setbeamertemplate{section-in-toc}[gotham-simple]
2817 \setbeamertemplate{subsection-in-toc}[gotham-simple]
2818 \setbeamertemplate{subsubsection-in-toc}[gotham-simple]
2819 \setbeamertemplate{background-canvas}[toc-subsection-gotham]
2820 \setbeamertemplate{frametitle}[toc-gotham]
2821 % \usebeamertemplate*{subsection-page}% already included
2822 }

```

(End of definition for `\defbeamertemplate{toc-part-frame}{gotham-simple}`. This function is documented on page ??.)

`amertemplate{toc-part-frame}{gotham-bullet}` Definition of the toc in part | section | subsection templates for gotham bullet style.

The following test files are used for this code: `gotham-test-042`.

```

2823 \defbeamertemplate{toc-part-frame}{gotham-bullet}{
2824   \setbeamertemplate{part-in-toc}[gotham-bullet]
2825   \setbeamertemplate{section-in-toc}[gotham-bullet]
2826   \setbeamertemplate{subsection-in-toc}[gotham-bullet]
2827   \setbeamertemplate{subsubsection-in-toc}[gotham-bullet]
2828   \setbeamertemplate{background-canvas}[toc-part-gotham]
2829   \setbeamertemplate{frametitle}[toc-gotham]
2830   % \usebeamertemplate*{part-page}% already included
2831 }
2832 \defbeamertemplate{toc-section-frame}{gotham-bullet}{
2833   \setbeamertemplate{part-in-toc}[gotham-bullet]
2834   \setbeamertemplate{section-in-toc}[gotham-bullet]
2835   \setbeamertemplate{subsection-in-toc}[gotham-bullet]
2836   \setbeamertemplate{subsubsection-in-toc}[gotham-bullet]
2837   \setbeamertemplate{background-canvas}[toc-section-gotham]
2838   \setbeamertemplate{frametitle}[toc-gotham]%
2839   % \usebeamertemplate*{section-page}% already included
2840 }
2841 \defbeamertemplate{toc-subsection-frame}{gotham-bullet}{
2842   \setbeamertemplate{part-in-toc}[gotham-bullet]
2843   \setbeamertemplate{section-in-toc}[gotham-bullet]
2844   \setbeamertemplate{subsection-in-toc}[gotham-bullet]
2845   \setbeamertemplate{subsubsection-in-toc}[gotham-bullet]
2846   \setbeamertemplate{background-canvas}[toc-subsection-gotham]
2847   \setbeamertemplate{frametitle}[toc-gotham]
2848   % \usebeamertemplate*{subsection-page}% already included
2849 }

```

(End of definition for `\defbeamertemplate{toc-part-frame}{gotham-bullet}`. This function is documented on page ??.)

-]`\begin{frame}[tocpart]` Add a frame option `tocpart` to display the `tocpart` frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-042.

```

2850 \bool_new:N \l_gotham_tocpartframe
2851 \bool_set_false:N \l_gotham_tocpartframe
2852 \define@key{beamerframe}{tocpart}[true]{
2853   \bool_set_true:N \l_gotham_tocpartframe
2854   \begingroup
2855     \usebeamertemplate{toc~part~frame}
2856 }
2857 \apptocmd{\beamer@resetecodes}{
2858   \bool_if:NTF \l_gotham_tocpartframe {
2859     \endgroup
2860     \bool_set_false:N \l_gotham_tocpartframe
2861   }{}}
2862 }{}{}%
2863 % \define@key{beamerframe}{tocpart}[true]{
2864 %   \thispagestyle[navigation@tocpart]
2865 %
2866 % \def\ps@navigation@tocpart{
2867 %   \usebeamertemplate{toc~part~frame}
2868 %   \c@nameuse{ps@navigation}
2869 %

```

(End of definition for `\begin{frame}[tocpart]`. This function is documented on page 31.)

-]`\begin{frame}[tocsec]` Add a frame option `tocsec` to display the `tocsec` frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-042.

```

2870 \bool_new:N \l_gotham_tocsectionframe
2871 \bool_set_false:N \l_gotham_tocsectionframe
2872 \define@key{beamerframe}{tocsec}[true]{
2873   \bool_set_true:N \l_gotham_tocsectionframe
2874   \begingroup
2875     \usebeamertemplate{toc~section~frame}
2876 }
2877 \apptocmd{\beamer@resetecodes}{
2878   \bool_if:NTF \l_gotham_tocsectionframe {
2879     \endgroup

```

```

2880     \bool_set_false:N \l_gotham_tocsectionframe
2881   }{ }
2882 }{ }{ }
2883 % \define@key{beamerframe}{tocsec}[true]{
2884 %   \thispagestyle{navigation@tocsec}
2885 %
2886 % \def\ps@navigation@tocsec{
2887 %   \usebeamertemplate{toc~section~frame}
2888 %   \nameuse{ps@navigation}
2889 %

```

(End of definition for `\begin{frame}[tocsec]`. This function is documented on page 31.)

- `]\begin{frame}[tocsubsec]` Add a frame option `tocsubsec` to display the `tocsubsec` frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: `gotham-test-042`.

```

2890 \bool_new:N \l_gotham_tocsubsectionframe
2891 \bool_set_false:N \l_gotham_tocsubsectionframe
2892 \define@key{beamerframe}{tocsubsec}[true]{
2893   \bool_set_true:N \l_gotham_tocsubsectionframe
2894   \begingroup
2895     \usebeamertemplate{toc~subsection~frame}
2896   }
2897 \apptocmd{\beamer@resetecodes}{%
2898   \bool_if:NTF \l_gotham_tocsubsectionframe {
2899     \endgroup
2900   \bool_set_false:N \l_gotham_tocsubsectionframe
2901 }{}}
2902 }{ }{ }
2903 % \define@key{beamerframe}{tocsubsec}[true]{
2904 %   \thispagestyle{navigation@tocsubsec}
2905 %
2906 % \def\ps@navigation@tocsubsec{
2907 %   \usebeamertemplate{toc~subsection~frame}
2908 %   \nameuse{ps@navigation}
2909 %

```

(End of definition for `\begin{frame}[tocsubsec]`. This function is documented on page 31.)

- `]\begin{frame}[tocsubsubsec]` Add a frame option `tocsubsubsec` to display the `tocsubsubsec` frame template. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-042.

```
2910 \bool_new:N \l_gotham_tocsubsubsectionframe
2911 \bool_set_false:N \l_gotham_tocsubsubsectionframe
2912 \define@key{beamerframe}{tocsubsubsection}{true}{
2913   \bool_set_true:N \l_gotham_tocsubsubsectionframe
2914   \begingroup
2915     \usebeamertemplate{toc~subsubsection~frame}
2916 }
2917 \apptocmd{\beamer@resetecodes}{%
2918   \bool_if:NTF \l_gotham_tocsubsubsectionframe {
2919     \endgroup
2920     \bool_set_false:N \l_gotham_tocsubsubsectionframe
2921   }{}}
2922 }{}{}%
2923 % \define@key{beamerframe}{tocsubsubsection}{true}%
2924 %   \thispagestyle{navigation@tocsubsubsection}%
2925 %
2926 % \def\ps@navigation@tocsubsubsection{%
2927 %   \usebeamertemplate{toc~subsubsection~frame}%
2928 %   \nameuse{ps@navigation}%
2929 % }
```

(End of definition for `\begin{frame}[tocsubsubsection]`. This function is documented on page 32.)

`inner_key_interface` Controls the inner settings for `parttocframe` (or `secttocframe`, `subsecttocframe` respectively).

The following test files are used for this code: gotham-test-041.

```
2930 \keys_define:nn { gotham / inner }%
2931 {%
2932   % TOC style
2933   tocframe-template .usage:n = { general },
2934   tocframe-template .default:n = { gotham~bullet },
2935   tocframe-template .code:n = { \__gotham_set_template:nn{toc~page}{#1} }%
2936 }%
2937
2938 \keys_define:nn { gotham / inner }{%
2939   % parttocframe template
2940   parttocframe-template .usage:n = { general },
2941   parttocframe-template .default:n = { gotham~simple },
2942   parttocframe-template .code:n = { \__gotham_set_template:nn{toc~part~frame}{#1} }%
2943 }%
2944 \keys_define:nn { gotham / inner }
```

```

2945 {
2946 % parttocframe default
2947 parttocframe~default .choice:, 
2948 parttocframe~default .usage:n = { general },
2949 parttocframe~default .default:n = { true },
2950
2951 parttocframe~default / true .code:n = { \booltrue{partContent} },
2952 parttocframe~default / on .code:n = { \booltrue{partContent} },
2953 parttocframe~default / enable .code:n = { \booltrue{partContent} },
2954
2955 parttocframe~default / false .code:n = { \boolfalse{partContent} },
2956 parttocframe~default / off .code:n = { \boolfalse{partContent} },
2957 parttocframe~default / disable .code:n = { \boolfalse{partContent} },
2958
2959 parttocframe~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u }
2960 }
2961
2962 \keys_define:nn { gotham / inner }{
2963 % sectiontocframe template
2964 sectiontocframe~template .usage:n = { general },
2965 sectiontocframe~template .default:n = { gotham~simple },
2966 sectiontocframe~template .code:n = { \__gotham_set_template:nn{toc~section~frame}{#1} }
2967 }
2968 \keys_define:nn { gotham / inner }
2969 {
2970 % sectiontocframe default
2971 sectiontocframe~default .choice:, 
2972 sectiontocframe~default .usage:n = { general },
2973 sectiontocframe~default .default:n = { true },
2974
2975 sectiontocframe~default / true .code:n = { \booltrue{sectionContent} },
2976 sectiontocframe~default / on .code:n = { \booltrue{sectionContent} },
2977 sectiontocframe~default / enable .code:n = { \booltrue{sectionContent} },
2978
2979 sectiontocframe~default / false .code:n = { \boolfalse{sectionContent} },
2980 sectiontocframe~default / off .code:n = { \boolfalse{sectionContent} },
2981 sectiontocframe~default / disable .code:n = { \boolfalse{sectionContent} },
2982
2983 sectiontocframe~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u }
2984 }
2985
2986 \keys_define:nn { gotham / inner }{
2987 % subsectiontocframe template

```

```

2988 subsectionontocframe~template .usage:n = { general },
2989 subsectionontocframe~template .default:n = { gotham-simple },
2990 subsectionontocframe~template .code:n = { \__gotham_set_template:nn{toc~subsection~frame}{#1}
2991 }
2992 \keys_define:nn { gotham / inner }
2993 {
2994 % subsectionontocframe default
2995 subsectionontocframe~default .choice:,
2996 subsectionontocframe~default .usage:n = { general },
2997 subsectionontocframe~default .default:n = { true },
2998
2999 subsectionontocframe~default / true .code:n = { \booltrue{subsectionContent} },
3000 subsectionontocframe~default / on .code:n = { \booltrue{subsectionContent} },
3001 subsectionontocframe~default / enable .code:n = { \booltrue{subsectionContent} },
3002
3003 subsectionontocframe~default / false .code:n = { \boolfalse{subsectionContent} },
3004 subsectionontocframe~default / off .code:n = { \boolfalse{subsectionContent} },
3005 subsectionontocframe~default / disable .code:n = { \boolfalse{subsectionContent} },
3006
3007 subsectionontocframe~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1
3008 }

```

(End of definition for `inner` key - interface. This function is documented on page ??.)

Environments styles

`\gotham@blocksep` `blocksep` and `blockadjust` lengths used in `\gotham@block` definition. While `\gotham@strut` is a command to ensure verticale spacing equivalent to a line.

```

3009 \newlength{\gotham@blocksep}
3010 \newlength{\gotham@blockadjust}
3011 \setlength{\gotham@blocksep}{0.75ex}
3012 \setlength{\gotham@blockadjust}{0.25ex}
3013 \providecommand{\gotham@strut}{%
3014   \vphantom{ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz (/)}%
3015 }

```

(End of definition for `\gotham@blocksep` and `\gotham@blockadjust`. These variables are documented on page ??.)

`\gotham@parskip` length `parskip` defined by `gotham` and the `linespread` are adjusted.

```

\linespread
3016 \newlength{\gotham@parskip}
3017 \setlength{\gotham@parskip}{0.5em}
3018 \setlength{\parskip}{\gotham@parskip}

```

```
3019 \linespread{1.15}
```

(End of definition for \gotham@parskip and \linespread. These variables are documented on page ??.)

- \newcommand{\gotham@block}[1] The three different block environments differ only in their colours. Rather than repeat the essentially the same template three times, we use the auxiliary macro \gotham@block to define all three templates.

The following test files are used for this code: gotham-test-043.

```
3020 \providecommand{\gotham@block}[1]{  
3021   \par\vskip\medskipamount  
3022   \setlength{\parskip}{0pt}  
3023  
3024   % If a background color is defined for the block title or body, we need to add a little bit  
3025   % Ideally, this would be accomplished by setting |colsep=0.75ex|, which is intended to add  
3026   % Unfortunately, |colsep| also adds this separation if the background color is inherited, e  
3027   % (The technical reason for this boils down to the fact that the |\ifx| directive does not  
3028   %  
3029   % To achieve the correct spacing for |alertblock|s and |exampleblock|s as well as for norma  
3030   %  
3031   % If the |block title| background is empty, or the user has explicitly removed the backgrou  
3032   \ifbeamercolorempty[bg]{block~title#1}{%  
3033     \begin{beamercolorbox}[rightskip=0pt-plus~4em]{block~title#1}  
3034   }{  
3035     \ifbeamercolorempty[bg]{block~title}{  
3036       \begin{beamercolorbox}[rightskip=0pt-plus~4em]{block~title#1}  
3037     }  
3038     % Otherwise, if the |block title| has a background, we set the padding based on |\gotham@  
3039     % However, we have to visually compensate for the |\gotham@strut| added to the block title  
3040     %  
3041   }  
3042   \begin{beamercolorbox}[  
3043     sep=\dimexpr\gotham@blocksep-\gotham@blockadjust\relax,  
3044     leftskip=\gotham@blockadjust,  
3045     rightskip=\dimexpr\gotham@blockadjust~plus~4em\relax,  
3046   ]{block~title#1}  
3047   }  
3048 }  
3049 % We can now set the contents of the |block title|.  
3050 % The zero-width but positive-height box |\gotham@strut| ensures that the block title box h  
3051 %  
3052 \usebeamertfont*{block~title#1}  
3053 \gotham@strut
```

```

3054   \insertblocktitle
3055   \gotham@strut
3056   \end{beamercolorbox}
3057   % Next, we typeset the |block body|.
3058   % This the code is similar to, but simpler than, the |block title| code since we don't need
3059   \nointerlineskip
3060   \ifbeamercolorempty[bg]{block~body#1}{
3061     \begin{beamercolorbox}[vmode]{block~body#1}
3062   }{
3063     \ifbeamercolorempty[bg]{block~body}{

3064       \begin{beamercolorbox}[vmode]{block~body#1}
3065     }{
3066       \begin{beamercolorbox}[sep=\gotham@blocksep, vmode]{block~body#1}
3067         \vspace{-\gotham@parskip}
3068       }
3069     }
3070     \usebeamertfont{block~body#1}
3071     \setlength{\parskip}{\gotham@parskip}
3072   }
3073   % This concludes the auxiliary macro |\gotham@block|.

```

(End of definition for `\newcommand{\gotham@block}{[1]}`. This function is documented on page ??.)

`\defbeamertemplate{block-begin}{gotham}` We could define the block beamer templates using the auxiliary macro `\gotham@block`.... Yet, following the precious advice from Sam Carter <https://github.com/jolars/moloch/issues/6>, we should keep beamer blocks. But of course, one can go back to metropolis style using the commented lines here.

The following test files are used for this code: *gotham-test-043*.

```

3074 % \defbeamertemplate*{block~begin}{gotham}{\gotham@block{}}
3075 % \defbeamertemplate*{block~alerted~begin}{gotham}{\gotham@block{~alerted}}
3076 % \defbeamertemplate*{block~example~begin}{gotham}{\gotham@block{~example}}
3077 % \defbeamertemplate*{block~end}{gotham}{\end{beamercolorbox}\vspace*{0.2ex}}
3078 % \defbeamertemplate*{block~alerted~end}{gotham}{\end{beamercolorbox}\vspace*{0.2ex}}
3079 % \defbeamertemplate*{block~example~end}{gotham}{\end{beamercolorbox}\vspace*{0.2ex}}

```

(End of definition for `\defbeamertemplate{block-begin}{gotham}`. This function is documented on page ??.)

`\defbeamertemplate{block-begin}{gotham}` We define the block beamer templates using the auxiliary macro `\gotham@block`.

The following test files are used for this code: *gotham-test-043*.

```
3080 \defbeamertemplate*{itemize~item}{gotham}{%\textbullet{}}
```

```

3081 \large
3082 \setbeamertemplate{itemize-item}{circle}
3083 \usebeamertemplate{itemize-item}
3084 }
3085 \defbeamertemplate*{itemize-subitem}{gotham}{\%$\\blacktriangleright$}
3086 \scriptsize
3087 \setbeamertemplate{itemize-subitem}{triangle}
3088 \usebeamertemplate{itemize-subitem}
3089 }
3090 \defbeamertemplate*{itemize-subsitem}{gotham}{\%square or -
3091 \tiny
3092 \$\\blacksquare\$ \% \\textbf{-}
3093 \% \\setbeamertemplate{itemize-subsitem}{square}
3094 \% \\usebeamertemplate{itemize-subsitem} \% not working because the size of the square is ha
3095 }
3096
3097 %% TRY: enumitem package, enumitem and beamer are incompatible.
3098 % \\setitemize{label=\\usebeamertemplate*{itemize-item}}
3099 %   \\usebeamercolor[fg]{itemize-item}
3100 %   \\usebeamertemplate{itemize-item}}
3101 %% I tried to redefine everything to make them compatible, but it breaks the [alert] environ
3102

```

(End of definition for `\defbeamertemplate{block-begin}{gotham}`. This function is documented on page ??.)

`\defbeamertemplate{caption}` Templates definitions for caption and footnote.

`\defbeamertemplate{footnote}` The following test files are used for this code: gotham-test-043.

```

3103 \defbeamertemplate*{caption-label-separator}{gotham}{:~}
3104 \setbeamertemplate{caption}[numbered]
3105 \defbeamertemplate*{footnote}{gotham}{%
3106   \\parindent\\oem\\noindent
3107   \\raggedright
3108   \\usebeamercolor{footnote}\\hbox{to\\sim0.8em{\\hfill\\insertfootnotemark}}\\insertfootnotetext\\par
3109 }

```

(End of definition for `\defbeamertemplate{caption}` and `\defbeamertemplate{footnote}`. These functions are documented on page 32.)

`Default_inner_keys` Apply default key options.

The following test files are used for this code: gotham-test-043.

```

3110 \% when no value is given, default is called.

```

```

3111 \keys_set:nn { gotham / inner } {
3112   title~page,
3113   watermark~template, watermark~default,
3114   standout~template, standin~template,
3115   partframe~template, partframe~default,
3116   sectionframe~template, sectionframe~default,
3117   subsectionframe~template, subsectionframe~default,
3118   subsubsectionframe~template, subsubsectionframe~default,
3119   tocframe~template,
3120   parttocframe~template, parttocframe~default,
3121   sectiontocframe~template, sectiontocframe~default,
3122   subsectiontocframe~template, subsectiontocframe~default,
3123   % subsubsectiontocframe~template, subsubsectiontocframe~default,
3124 }

```

(End of definition for *Default inner keys*. This function is documented on page ??.)

`Process_inner_keys` Process package options.

The following test files are used for this code: *gotham-test-043*.

```

3125 \ProcessKeyOptions[ gotham / inner ]
3126 % \mode<all>

```

(End of definition for *Process inner keys*. This function is documented on page ??.)

```

3127 \%endinput
3128 </inner>

```

```

3129 <*outer>
3130 \ProvidesExplPackage{beamerouterthemegotham}{2024-11-11}{1.2.0.a}{gotham outer theme}
3131 \RequirePackage{expl3}
3132 \RequirePackage{xfp}
3133 \RequirePackage{calc}
3134 \RequirePackage{tikz}

```

OUTER

`Compatibility_mode_for_colors` FROM COLOR THEME: useful to provide this recall when the inner theme is loaded without the color theme.

```

3135 \@ifundefined{\string\color@colorProgBar}{
3136   \providebool{darkBG} \boolfalse{darkBG}
3137   \providebool{transparentBG} \booltrue{transparentBG}

```

```

3138 \colorlet{colorBG}{white}
3139 \colorlet{colorFG}{black}
3140 \colorlet{colorFrametitle}{purple}
3141 \colorlet{colorStandout}{purple}
3142 \colorlet{colorStandin}{purple}
3143 \colorlet{colorTitlepage}{purple}
3144 \colorlet{colorFiligrane}{gray}
3145 \colorlet{colorBackElement}{gray}
3146 \colorlet{colorProgBar}{orange}
3147 \colorlet{colorAlert}{red}
3148 \colorlet{colorExample}{green}
3149 \setbeamercolor{progress~bar}{
3150   use=alerted~text,
3151   fg=colorProgBar,
3152   bg=alerted~text.fg!50!black!30
3153 }
3154 \setbeamercolor{progress~bar~in~head/foot}{%
3155   use=progress~bar,
3156   parent=progress~bar
3157 }
3158 \setbeamercolor{progress~bar~in~part~page}{%
3159   use=progress~bar,
3160   parent=progress~bar
3161 }
3162 \setbeamercolor{progress~bar~in~section~page}{%
3163   use=progress~bar,
3164   parent=progress~bar
3165 }
3166 \setbeamercolor{progress~bar~in~splitvert}{%
3167   use=progress~bar,
3168   parent=progress~bar
3169 }
3170 \setbeamercolor{frametitleSection}{use=primary~palette, bg=, fg=primary~palette.bg}
3171 \setbeamercolor{standout}{use=primary~palette, bg=colorStandout, fg=primary~palette.bg}
3172 \setbeamercolor{standin}{use=normal~text, bg=colorStandin, fg=normal~text.fg}
3173 \setbeamercolor{section~in~toc}{use=normal~text, parent=normal~text,}
3174 \setbeamercolor{subsection~in~toc}{use=normal~text, parent=normal~text,}
3175 \setbeamercolor{subsubsection~in~toc}{use=normal~text, parent=normal~text,}
3176 }{
3177 % else the colors are defined: this is fine.
3178 }

```

(End of definition for *Compatibility mode for colors*. This function is documented on page ??.)

\l__gotham_template_name_prop Dictionary/map of template elements and predefined option according to the context.
 Naming convention: template/What/Who, i.e. Name: key=background canvas/watermark, value = gotham draft

```

3179 \prop_if_exist:NTF \l__gotham_template_name_prop
3180 {}{
3181   % if not defined than define it.
3182   \prop_new:N \l__gotham_template_name_prop
3183 }
```

(End of definition for \l__gotham_template_name_prop.)

\l__gotham_tmpa_seq tmp variables

```

\l__gotham_tmpa_tl
\l__gotham_tmpb_tl
3184 \seq_if_exist:NTF \l__gotham_tmpa_seq
3185 {}{
3186   % sequence
3187   \seq_new:N \l__gotham_tmpa_seq
3188 }
3189 \tl_if_exist:NTF \l__gotham_tmpa_tl
3190 {}{
3191   % token list A
3192   \tl_new:N \l__gotham_tmpa_tl
3193 }
3194 \tl_if_exist:NTF \l__gotham_tmpb_tl
3195 {}{
3196   % token list B
3197   \tl_new:N \l__gotham_tmpb_tl
3198 }
```

(End of definition for \l__gotham_tmpa_seq, \l__gotham_tmpa_tl, and \l__gotham_tmpb_tl.)

__gotham_set_prop_template:nn

#1 : element name (from beamer doc) in other word, the name the template category
#2 : prefined option (from beamer doc)

Function that store in a map the name a template use later. The following naming convention is used: Template/What/Who Name: watermark/gotham draft. This means for example that if a beamer template is defined using `\defbeamertemplate{background}{watermark/gotham}` then the function has to be call using `__gotham_set_prop_template{background/watermark}{gotham}` that will filled internally the map using the l3 command `\prop_put:Nnn \l__gotham_template_name_prop {#1} {#2}`. If the template name given as input does not exist, an error is raised.

The following test files are used for this code: gotham-test-044.

```
3199 \cs_if_exist:NTF \__gotham_set_prop_template:nn {}{  
3200   % if it doesn't exist, then create it.  
3201   \cs_new_protected:Nn \__gotham_set_prop_template:nn  
3202   {  
3203     % Check if the first argument contains a /  
3204     \tl_if_in:nnTF {#1} { / }  
3205     {  
3206       % Split the first around the /  
3207       \seq_set_split:Nnn \l__gotham_tmpa_seq { / } {#1}  
3208       \tl_set:Nn \l__gotham_tmpa_tl { \seq_item:Nn \l__gotham_tmpa_seq { 1 } }  
3209       \tl_set:Nn \l__gotham_tmpb_tl { \seq_item:Nn \l__gotham_tmpa_seq { 2 } }  
3210       % Check if template exist  
3211       \cs_if_exist:cTF {beamer@@tmpop@}\exp_not:V \l__gotham_tmpa_tl @\exp_not:V \l__gotham_tmpb_tl @  
3212       % set the value in the map, so it can be called later.  
3213       \prop_put:Nnn \l__gotham_template_name_prop {#1} {#2}  
3214       % \setbeamertemplate{#1}[#2]  
3215     }{  
3216       \PackageError{beamerthemegotham}{  
3217         {The-beamer-template-named-' \l__gotham_tmpa_tl '-with-the-option-' \l__gotham_tmpb_tl /#2' -  
3218           helping-message}  
3219     }  
3220   }% false -> error  
3221   \PackageError{beamerthemegotham}{  
3222   {  
3223     When-using-' \c_underscore\cs_to_str:N \__gotham_set_prop_template'-the-first-argument  
3224     As-example:-if-' \c_underscore\str defbeamertemplate{background}{watermark/gotham-draft}' -  
3225     }{helping-message}  
3226   }  
3227 }  
3228 }
```

__gotham_add_beamerframe_key:n

#1 : Name of the option to add, this name should also correspond to the name of the environment followed by the suffix 'env'.

Function to add an option of a frame using an environment. For example, if the name 'optionA' is the argument given to the function, an frame option named 'optionA' will be added, and this option will surround the frame with the environment named 'optionAenv'. So, the environment 'optionA' must have been declared before.

The following test files are used for this code: gotham-test-038.

```
3229 \seq_if_exist:NTF \l__gotham_frameoption_tmp_seq {}{  
3230   % Define the sequence of frameoptions environments to close  
3231   \seq_new:N \l__gotham_frameoption_tmp_seq  
3232 }  
3233  
3234 \cs_if_exist:NTF \__gotham_add_beamerframe_key:n {}{  
3235   % if it doesn't exist, then create it.  
3236  
3237   % Define the command to add frameoptions  
3238   \cs_new_protected:Nn \__gotham_add_beamerframe_key:n {  
3239     \define@key{beamerframe}{#1}[true]{  
3240       \begin{#1env}  
3241         \seq_put_left:Nn \l__gotham_frameoption_tmp_seq { \end{#1env} }  
3242       }  
3243     }  
3244  
3245   % At the end of frames close the opened environments.  
3246   \apptocmd{\beamer@reseteecodes}{  
3247     % Join elements in the queue without separator then output the result  
3248     \seq_use:Nn \l__gotham_frameoption_tmp_seq {}  
3249     % clear working queue  
3250     \seq_clear:N \l__gotham_frameoption_tmp_seq  
3251   }{}{  
3252 }
```

__gotham_set_template:nn

#1 : element name (from beamer doc) in other word, the name the template category
#2 : prefined option (from beamer doc)

Function to set a beamertemplate with an option if it exists, otherwise an error is raised.
Unfortunatly, (as far as I know) it not possible to test if the element name exists independently from the prefined option.

The following test files are used for this code: gotham-test-038.

```
3253 \cs_if_exist:NTF \_\_gotham\_set\_template:nn {}{  
3254   % If it doesn't exist, then create it.  
3255  
3256   % Define the command to set template if it exists.  
3257   \cs_new_protected:Nn \_\_gotham\_set\_template:nn  
3258   {  
3259     \cs_if_exist:cTF {beamer@@tmpop@#1#2} {  
3260       \setbeamertemplate{#1}{#2}  
3261     }{  
3262       \PackageError{beamerinnerthemegotham}{  
3263         {The-beamer-template-named-'#1'-with-the-option-'#2'-does-not-exist}  
3264         {helping-message unknown setbeamertemplate option}  
3265       }  
3266     }  
3267   }
```

Sidebars

\sidebarRightHOffset

lengths between borders (right and left) and the commands (\gothamRightFiligrane and \gothamLeftFiligrane) used inside \setbeamertemplate{sidebar~canvas~right}[default/gotham] (left respectively).

The following test files are used for this code: gotham-test-044.

```
3268 % sidebar lengths  
3269 \newlength{\sidebarRightHOffset}  
3270 \setlength{\sidebarRightHOffset}{-2.5ex}  
3271 \newlength{\sidebarLeftHOffset}  
3272 \setlength{\sidebarLeftHOffset}{+0.5ex}
```

(End of definition for \sidebarRightHOffset and \sidebarLeftHOffset. These variables are documented on page 33.)

\gothamRightFiligrane

Commands used internally by \setbeamertemplate{sidebar~canvas~right}[default/gotham-filigrane] (left respectively), that are empty by default. But these commands can be simply rede-

fined to custom watermarks (filigrane) in sidebars.

The following test files are used for this code: gotham-test-044.

```
3273 % Command to add filigrane/edging in sidebar
3274 \providecommand{\gothamRightFiligrane}{
3275   % left empty intentionally
3276   % \rotatebox{90}{gotham right filigrane pattern}
3277 }
3278 \providecommand{\gothamLeftFiligrane}{
3279   % left empty intentionally
3280   % \rotatebox{-90}{\hspace*{5em} gotham left filigrane pattern}
3281 }
```

(End of definition for \gothamRightFiligrane and \gothamLeftFiligrane. These functions are documented on page 33.)

\defbeamertemplate{sidebar~canvas~right}{} Definitions of \defbeamertemplate{sidebar~canvas~right} (respectively \defbeamertemplate{sideb

\defbeamertemplate{sidebar~canvas~left}{} that are used by gotham by default.

The following test files are used for this code: gotham-test-044.

```
3282 \defbeamertemplate{sidebar-right}{default/beamer}{
3283   \vfill
3284   \llap{\insertlogo\hskip0.1cm}
3285   \vskip2pt
3286   \llap{\usebeamertemplate***{navigation-symbols}\hskip0.1cm}
3287   \vskip2pt
3288 }
3289 \defbeamertemplate{sidebar-right}{default/empty}{}
3290 \defbeamertemplate{sidebar~canvas~right}{default/empty}{}
3291 \defbeamertemplate{sidebar~canvas~right}{default/gotham-filigrane}{
3292   % pull to the left otherwise, the filigrane is outside of the frame.
3293   \hspace*{\sidebarRightHOffset}
3294   \gothamRightFiligrane
3295 }
3296 \defbeamertemplate{sidebar-left}{default/empty}{}
3297 \defbeamertemplate{sidebar~canvas~left}{default/empty}{}
3298 \defbeamertemplate{sidebar~canvas~left}{default/gotham-filigrane}{
3299   \hspace*{\sidebarLeftHOffset}
3300   \gothamLeftFiligrane
3301 }
3302 % Add the template to the prop (dictionary) of background template to use according to the s
3303 \prop_put:Nnn \l__gotham_template_name_prop {sidebar~canvas~left/default} {gotham-filigrane}
3304 \prop_put:Nnn \l__gotham_template_name_prop {sidebar~canvas~right/default} {gotham-filigrane}
```

```

3305 \prop_put:Nnn \l__gotham_template_name_prop {sidebar~left/default} {empty}
3306 \prop_put:Nnn \l__gotham_template_name_prop {sidebar~right/default} {beamer}

```

(End of definition for `\defbeamertemplate{sidebar~canvas~right}{}` and `\defbeamertemplate{sidebar~canvas~left}{}`.
These functions are documented on page ??.)

\l_gotham_defaultEdging Boolean variable to display the edging by default (or not).

The following test files are used for this code: gotham-test-044.

```

3307 \bool_new:N \l_gotham_defaultEdging
3308 \bool_set_false:N \l_gotham_defaultEdging
3309 % At every new frame, reset the options to default (unless some options/keys are given)
3310 \BeforeBeginEnvironment{frame} {
3311   \bool_if:NTF \l_gotham_defaultEdging {
3312     \setbeamertemplate{sidebar~canvas~left}[default/\prop_item:Nn \l__gotham_template_name_prop]
3313     \setbeamertemplate{sidebar~canvas~right}[default/\prop_item:Nn \l__gotham_template_name_prop]
3314   }{
3315     % false
3316     \setbeamertemplate{sidebar~canvas~left}[default/empty]
3317     \setbeamertemplate{sidebar~canvas~right}[default/empty]
3318   }
3319 }

```

(End of definition for `\l_gotham_defaultEdging`. This function is documented on page 33.)

]\begin{frame}[edging] Add a frame option `edging` to display an empty sidebar canvas canvas. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-044.

```

3320 % bool to trigger the add of edging in sidebar canvas
3321 \newenvironment{edgingenv} {
3322   \setbeamertemplate{sidebar~canvas~left}[
3323     default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~canvas~left/default}
3324   ]
3325   \setbeamertemplate{sidebar~canvas~right}[
3326     default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~canvas~right/default}
3327   ]
3328 }{}
3329 \__gotham_add_beamerframe_key:n {edging}

```

(End of definition for `\begin{frame}[edging]`. This function is documented on page 33.)

-]`\begin{frame}[noedging]` Add a frame option `noedging` to do not display an empty sidebar canvas canvas. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-044.

```
3330 % bool to trigger the add of noedging in sidebar canvas
3331 \newenvironment{noedgingenv}{
3332   \setbeamertemplate{sidebar-canvas-left}[default/empty]
3333   \setbeamertemplate{sidebar-canvas-right}[default/empty]
3334 }{}
3335 \__gotham_add_beamerframe_key:n {noedging}
```

(End of definition for `\begin{frame}[noedging]`. This function is documented on page 33.)

- `outer_key_interface` Controls the outer settings for sidebar canvas right and sidebar canvas left.

The following test files are used for this code: gotham-test-044.

```
3336 \keys_define:nn { gotham / outer }
3337 {
3338   % sidebar-canvas-right template
3339   sidebar-canvas-right-template .usage:n = { general },
3340   sidebar-canvas-right-template .default:n = { gotham-filigrane },
3341   sidebar-canvas-right-template .code:n = { \__gotham_set_prop_template:nn{sidebar-canvas-right}{#1} }
3342 }
3343 \keys_define:nn { gotham / outer }
3344 {
3345   % sidebar-canvas-left template
3346   sidebar-canvas-left-template .usage:n = { general },
3347   sidebar-canvas-left-template .default:n = { gotham-filigrane },
3348   sidebar-canvas-left-template .code:n = { \__gotham_set_prop_template:nn{sidebar-canvas-left}{#1} }
3349 }
3350 \keys_define:nn { gotham / outer }{
3351   % edging default
3352   edging-default .choice:,,
3353   edging-default .usage:n = { general },
3354   edging-default .default:n = { false },
3355
3356   edging-default / true .code:n = { \bool_set_true:N \l_gotham_defaultEdging },
3357   edging-default / on .code:n = { \bool_set_true:N \l_gotham_defaultEdging },
3358   edging-default / enable .code:n = { \bool_set_true:N \l_gotham_defaultEdging },
3359
3360   edging-default / false .code:n = { \bool_set_false:N \l_gotham_defaultEdging },
3361   edging-default / off .code:n = { \bool_set_false:N \l_gotham_defaultEdging },
```

```

3362   edging-default / disable .code:n = { \bool_set_false:N \l_gotham_defaultEdging },
3363
3364   edging-default / unknown .code:n = { \PackageWarning{ gotham } { The-choice~'#1'~is~unknown }
3365 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

Navigation & Logo

\beamertemplate*{navigation-symbols}{empty} Apply the empty navigation symbol template by default.

The following test files are used for this code: gotham-test-045.

```

3366 \defbeamertemplate*{navigation-symbols}{empty}{}{}
```

(End of definition for \defbeamertemplate{navigation-symbols}{empty}. This function is documented on page ??.)*

\beamertemplate{navigation-symbols}{horizontal} From Beamer default theme.

The following test files are used for this code: gotham-test-045.

```

3367 % \setbeamertemplate{navigation-symbols}[vertical]
3368 % \setbeamertemplate{navigation-symbols}[only-frame-symbol]
3369 % \setbeamertemplate{navigation-symbols}[default] = horizontal
3370 % \defbeamertemplate{navigation-symbols}{horizontal}{
3371 %   \usebeamercolor[fg]{navigation-symbols}
3372 %   \insertslidenavigationsymbol
3373 %   \insertframenavigationsymbol
3374 %   \insertsubsectionnavigationsymbol
3375 %   \insertsectionnavigationsymbol
3376 %   \insertdocnavigationsymbol
3377 %   \insertbackfindforwardnavigationsymbol
3378 % }
```

(End of definition for \defbeamertemplate{navigation-symbols}{horizontal}. This function is documented on page ??.)

\beamertemplate{logo}{empty} Template used sometimes to have no logo on specific frames.

The following test files are used for this code: gotham-test-045.

```

3379 \defbeamertemplate{logo}{empty}{}{}
```

(End of definition for \defbeamertemplate{logo}{empty}. This function is documented on page ??.)

-]`\begin{frame}[nologo]` Add a frame option `nologo`, if you do not want your logo to be displayed. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-045.

```
3380 % bool to trigger the add of nologo action on frame.
3381 \newenvironment{nologoenv}{
3382   \setbeamertemplate{logo}{empty}
3383 }
3384 \__gotham_add_beamerframe_key:n {nologo}
```

(End of definition for `\begin{frame}[nologo]`. This function is documented on page 34.)

Headline & Frametitle

Headline

- `defbeamertemplate{headline}{default/gotham}` The headline template is empty by default by can be changed when using progress bar or the current section.

The following test files are used for this code: gotham-test-046, gotham-test-046b, gotham-test-047.

```
3385 \defbeamertemplate{headline}{default/gotham} {}
3386 \prop_put:Nnn \l__gotham_template_name_prop {headline/default} {gotham}
```

(End of definition for `\defbeamertemplate{headline}{default/gotham}`. This function is documented on page ??.)

- `rtemplate{headline}{default/gotham-section}` The headline template used to print the current section name and subsection. This template is used with `circlehead` progress bar

The following test files are used for this code: gotham-test-046, gotham-test-046b, gotham-test-047.

```
3387 \defbeamertemplate{headline}{default/gotham-section} {
3388   \begin{beamercolorbox}[wd=1.0\paperwidth, ht=2.5ex, dp=1.4ex, left]{headfoot}
3389     \usebeamertemplate{section-in-head/foot}\hspace*{3.5ex}
3390   \end{beamercolorbox}
3391 }
```

(End of definition for `\defbeamertemplate{headline}{default/gotham-section}`. This function is documented on page ??.)

Frametitle

```
\gothamFrametitleToppading  
  \gothamFrametitleBottompadding  
\gothamFrametitleLeftpadding  
\gothamFrametitleRightpadding
```

Dimensions of lengths used in the frametitle: top, bottom, left and right padding. All of them are equal to 2.2ex by default.

```
3393 \newlength{\gothamFrametitleToppading}  
3394 \newlength{\gothamFrametitleBottompadding}  
3395 \newlength{\gothamFrametitleLeftpadding}  
3396 \newlength{\gothamFrametitleRightpadding}  
3397 \setlength{\gothamFrametitleToppading}{2.2ex}  
3398 \setlength{\gothamFrametitleBottompadding}{2.2ex}  
3399 \setlength{\gothamFrametitleLeftpadding}{2.2ex}  
3400 \setlength{\gothamFrametitleRightpadding}{2.2ex}  
3401 % \gotham@strut from inner  
3402 \providecommand{\gotham@strut}{  
3403 \vphantom{ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghijklmnopqrstuvwxyz ()}}  
3404 }
```

(End of definition for `\gothamFrametitleToppading` and others. These variables are documented on page 34.)

`\gotham@frametitlestrut@start`

```
\gotham@frametitlestrut@end
```

Commands used to control the space over and under the title in frametitle.

The following test files are used for this code: `gotham-test-046`, `gotham-test-046b`, `gotham-test-047`.

```
3405 \providecommand{\gotham@frametitlestrut@start}{  
3406   \rule{0pt}{\gothamFrametitleToppading +  
3407     \totalheightof{  
3408       \ifcsdef{gotham@frametitleformat}{\gotham@frametitleformat{X}}{X}  
3409     }  
3410   }  
3411 }  
3412 \providecommand{\gotham@frametitlestrut@end}{  
3413   \rule[-\gothamFrametitleBottompadding]{0pt}{\gothamFrametitleBottompadding}  
3414 }
```

(End of definition for `\gotham@frametitlestrut@start` and `\gotham@frametitlestrut@end`. These functions are documented on page ??.)

```
\gothamInstituteLogoSquare[height]\defbeamertemplate{includeLogo}{default/gotham-square} \gothamInstituteLogoSquare  
[<height>]
```

Command to include the desired logo and a template used to add it to the frametitle. For example you can do `\renewcommand{\gothamInstituteLogoSquare}[1][4ex]{\includegraphics[he`

The following test files are used for this code: gotham-test-046, gotham-test-047.

```
3415 \providecommand{\gothamInstituteLogoSquare}[1][4ex]{  
3416   \% \includegraphics[height=#1]{gotham-logo.pdf}  
3417 }  
3418 \defbeamertemplate{includeLogo}{default/gotham-square}{  
3419   \gothamInstituteLogoSquare  
3420 }  
3421 \prop_put:Nnn \l__gotham_template_name_prop {includeLogo/default} {gotham-square}
```

template{includeLogo}{default/gotham-circle} Template used in frametitle when the option `progress bar= circlehead` is activated.

The following test files are used for this code: gotham-test-046b.

```
3422 \defbeamertemplate{includeLogo}{default/gotham-circle}{  
3423   \gothamProgressCircle  
3424 }
```

(End of definition for \defbeamertemplate{includeLogo}{default/gotham-circle}. This function is documented on page ??.)

template{includeLogo}{default/gotham-circle} Template to make sure the logo will remain centered and to do not change the height of the line when included. This template is used to include logo in frametitle.

The following test files are used for this code: gotham-test-046b.

```
3425 \defbeamertemplate{instituteLogo}{default/gotham}{  
3426   \% \raisebox{lift}[height][depth]{text}  
3427   \raisebox{0pt}[0pt][0pt]{  
3428     \raisebox{.5\fontcharht\font`E-0.5\height}{  
3429       \% \setbeamertemplate{}[]  
3430       \setbeamertemplate{includeLogo}[default/\prop_item:Nn \l__gotham_template_name_prop {incl  
3431       \usebeamertemplate{includeLogo}  
3432     }  
3433   }  
3434 }  
3435 \prop_put:Nnn \l__gotham_template_name_prop {instituteLogo/default} {gotham}
```

(End of definition for \defbeamertemplate{includeLogo}{default/gotham-circle}. This function is documented on page ??.)

`\gothamFrameSubtitleSep` Hyphen used as separator between title of the frame and its subtitle (within frametitle template).

The following test files are used for this code: gotham-test-047.

```
3436 \providecommand{\gothamFrameSubtitleSep}{  
3437   % \\[-.42em] % if newline (as default Beamer)  
3438   % or if same line with a -- separator.  
3439   \\ ----  
3440 }
```

`\gothamFramesubtitleStrutend` Length used in `vspace` at the end of framesubtitle.

```
3441 \newlength{\gothamFramesubtitleStrutend}  
3442 \setlength{\gothamFramesubtitleStrutend}{0pt}  
3443 % \setlength{\gothamFramesubtitleStrutend}{-1.25ex} %% When \newcommand{\gothamFrameSubtitl
```

(End of definition for `\gothamFramesubtitleStrutend`. This variable is documented on page 35.)

`ate{frametitle}{default/gotham~subsameline}` Template for frametitle include subtitle on the same line and a logo a flushed left.

The following test files are used for this code: gotham-test-047.

```
3444 \defbeamertemplate{frametitle}{default/gotham~subsameline}{  
3445   \nointerlineskip  
3446   \begin{beamercolorbox}[  
3447     wd=\paperwidth,  
3448     sep=0pt,  
3449     leftskip=\gothamFrametitleLeftpadding,  
3450     rightskip=\gothamFrametitleRightpadding,  
3451   ]{frametitle}  
3452   \gotham@frametitlestrut@start  
3453   \insertframetitle  
3454   \ifx\insertframesubtitle\empty  
3455     %% if subtitle to the frame is empty  
3456   \else  
3457     %% if not empty: add subtitle  
3458     {\usebeamertfont{framesubtitle}\usebeamercolor[fg]{framesubtitle}\gothamFrameSubtitleSep \v  
3459       \vspace*{\gothamFramesubtitleStrutend}  
3460     \fi  
3461     \nolinebreak  
3462     %% Add logo  
3463     \hfill{  
3464       \setbeamertemplate{instituteLogo}[default]\prop_item:Nn \l__gotham_template_name_prop {in
```

```

3465     \usebeamertemplate{instituteLogo}
3466 }
3467 \gotham@frametitlestrut@end
3468 \end{beamercolorbox}
3469 }
3470 \prop_put:Nnn \l__gotham_template_name_prop {frametitle/default} {gotham~subsameLine}

```

(End of definition for \defbeamertemplate{frametitle}{default/gotham~subsameLine}. This function is documented on page ??.)

e{framesubtitle}{default/gotham~subnewline} Template for framesubtitle include subtitle on the same line and a logo a flushed left.

The following test files are used for this code: gotham-test-047.

```

3471 \dim_new:N \l__gotham_framesubtitle_subnewline_strutend_dim
3472 \defbeamertemplate{framesubtitle}{default/gotham~subnewline}{
3473     \nointerlineskip
3474     \begin{beamercolorbox}[
3475         wd=\paperwidth,
3476         sep=0pt,
3477         leftskip=\gothamFrametitleLeftpadding,
3478         rightskip=\gothamFrametitleRightpadding,
3479     ]{frametitle}
3480     % put the subtitle in a raisebox to have no influence on the result.
3481     \raisebox{0pt}[0pt][0pt]{
3482         \raisebox{-0.3ex}{%
3483             \usebeamertemplate{framesubtitle}{\usebeamercolor[fg]{framesubtitle}\insertframesubtitle}
3484         }
3485     }
3486     % add 1ex to take into account the subtitle height.
3487     \dim_set:Nn \l__gotham_framesubtitle_subnewline_strutend_dim {1.ex+\gothamFramesubtitleStrut}
3488     \vspace{\l__gotham_framesubtitle_subnewline_strutend_dim}
3489 \end{beamercolorbox}
3490 }
3491 \prop_put:Nnn \l__gotham_template_name_prop {framesubtitle/default} {gotham~subnewline}

```

(End of definition for \defbeamertemplate{framesubtitle}{default/gotham~subnewline}. This function is documented on page ??.)

e{framesubtitle}{default/gotham~subnewline} Template for frametitle and a logo a flushed left then the subtitle on a new line.

The following test files are used for this code: gotham-test-047.

```

3492 \defbeamertemplate{frametitle}{default/gotham~subnewline}{
3493     \nointerlineskip
3494     \begin{beamercolorbox}[

```

```

3495   wd=\paperwidth,
3496   sep=0pt,
3497   leftskip=\gothamFrametitleLeftpadding,
3498   rightskip=\gothamFrametitleRightpadding,
3499 ]{frametitle}
3500 \gotham@frametitlestrut@start
3501 \insertframetitle
3502 \nolinebreak
3503 \hfill{
3504   \setbeamertemplate{instituteLogo}[default/\prop_item:Nn \l__gotham_template_name_prop {institutelogo}]
3505   \usebeamertemplate{instituteLogo}
3506 }
3507 \gotham@frametitlestrut@end
3508 \end{beamercolorbox}
3509 % End of the frametitle box, start then use the subtitle template if needed.
3510 \ifx\insertframesubtitle\empty
3511   %% if subtitle to the frame is not empty
3512 \else
3513   % reduce vertical space to have a 1pt overlap, so no white line appears with vectorial views
3514   \vspace*{-1pt}
3515   % add the subtitle
3516   \setbeamertemplate{framesubtitle}[default/\prop_item:Nn \l__gotham_template_name_prop {framesubtitle}]
3517   % \setbeamertemplate{framesubtitle}{[framesubtitle/default]}
3518   \usebeamertemplate{framesubtitle}
3519 \fi
3520 }

```

(End of definition for \defbeamertemplate{framesubtitle}{default/gotham-subnewline}. This function is documented on page ??.)

`outer_key_interface` Controls the outer settings for frametitle and framesubtitle.

The following test files are used for this code: gotham-test-047.

```

3521 \keys_define:nn { gotham / outer }{
3522   % frametitle template
3523   frametitle~template .usage:n = { general },
3524   frametitle~template .default:n = { gotham~subsameLine },
3525   frametitle~template .code:n = {
3526     \__gotham_set_prop_template:nn{frametitle/default}{#1}
3527     \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
3528   }
3529 }
3530 \keys_define:nn { gotham / outer }{
3531   % frametitle template

```

```

3532   framesubtitle~template .usage:n = { general },
3533   framesubtitle~template .default:n = { gotham~subnewline },
3534   framesubtitle~template .code:n = {
3535     \__gotham_set_prop_template:nn{framesubtitle/default}{#1}
3536     \setbeamertemplate{framesubtitle}[default/\prop_item:Nn \l__gotham_template_name_prop {fra
3537   }
3538 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

Continuation

te{frametitle-continuation}{default/beamer} Template for numerotation of frametitle when a frame are continuing on sevral pages (allowed with the beamer option `allowframebreaks`). Beamer theme (by default) is using roman number with uppercase.

The following test files are used for this code: gotham-test-047.

```

3539 \defbeamertemplate{frametitle-continuation}{default/beamer}{
3540   \usebeamertemplate{frametitle}
3541   {
3542     \MakeUppercase{\romannumeral \insertcontinuationcount}
3543   }
3544 }
```

(End of definition for \defbeamertemplate{frametitle-continuation}{default/beamer}. This function is documented on page ??.)

plate{frametitle-continuation}{default/tot} Template for numerotation of frametitle when a frame are continuing on sevral pages (allowed with the beamer option `allowframebreaks`). This template is using arabic number slash over the total number of page for this frame.

The following test files are used for this code: gotham-test-047.

```

3545 \defbeamertemplate{frametitle-continuation}{default/tot}{
3546   \usebeamertemplate{frametitle}
3547   {
3548     \textmd{%
3549       [\insertcontinuationcount
3550       \,,/\,,%
3551       \the\numexpr\beamer@endpageofframe+1-\beamer@startpageofframe
3552       ]%
3553     }%
3554   }
3555 }
```

(End of definition for \defbeamertemplate{frametitle-continuation}{default/tot}. This function is documented on page ??.)

te{frametitle-continuation}{default/gotham} Template for numerotation of frametitle when a frame are continuing on sevral pages (allowed with the beamer option `allowframebreaks`). Gotham theme (by default) is using roman number with lowercase.

The following test files are used for this code: gotham-test-047.

```
3556 \defbeamertemplate{frametitle-continuation}{default/gotham}{  
3557   \usebeamertemplate{frametitle}  
3558 {  
3559   \%small  
3560   (\romannumeral \insertcontinuationcount)  
3561 }  
3562 }  
3563 \prop_put:Nnn \l__gotham_template_name_prop {frametitle-continuation/default} {gotham}
```

(End of definition for \defbeamertemplate{frametitle-continuation}{default/gotham}. This function is documented on page ??.)

`outer_key_-_interface` Controls the outer settings for frametitle continuation.

The following test files are used for this code: gotham-test-047.

```
3564 \keys_define:nn { gotham / outer }{  
3565   % frametitle template  
3566   frametitle-continuation-template .usage:n = { general },  
3567   frametitle-continuation-template .default:n = { gotham },  
3568   frametitle-continuation-template .code:n = {  
3569     \__gotham_set_prop_template:nn{frametitle-continuation/default}{#1}  
3570     \setbeamertemplate{frametitle-continuation}[default/\prop_item:Nn \l__gotham_template_name]  
3571   }  
3572 }
```

(End of definition for `outer key - interface`. This function is documented on page ??.)

Footer & Footline

Footline

\defbeamertemplate{footline}{empty} Empty footline template used when the option `nofootline` is given.

The following test files are used for this code: gotham-test-048.

```
3573 \defbeamertemplate{footline}{empty}{}
```

(End of definition for \defbeamertemplate{footline}{empty}. This function is documented on page ??.)

- \begin{frame}[nofootline] Add a frame option `nofootline` to do not display an empty footline. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-048.

```
3574 % bool to trigger the add of nofootline in frame.  
3575 \newenvironment{nofootlineenv}{  
3576   \setbeamertemplate{footline}{empty}  
3577 }{}  
3578 \__gotham_add_beamerframe_key:n {nofootline}
```

(End of definition for \begin{frame}[nofootline]. This function is documented on page 35.)

\gothamFootlineVOffset Lengths used in `footline` template.

```
\gothamFootlineHeight  
\gothamFootlineDepth  
3579 % Footline lengths  
3580 % space between to bottom of the text (or the footnote) and the footline  
3581 \newlength{\gothamFootlineVOffset}  
3582 \newlength{\gothamFootlineHeight}  
3583 \newlength{\gothamFootlineDepth}  
3584 \newlength{\gothamFootlineHRightOffset}  
3585  
3586 \setlength{\gothamFootlineVOffset}{-0.5ex}  
3587 \setlength{\gothamFootlineDepth}{0.1ex}  
3588 \setlength{\gothamFootlineHeight}{1.5ex}  
3589 \setlength{\gothamFootlineHRightOffset}{\spaceskip}
```

(End of definition for `\gothamFootlineVOffset`, `\gothamFootlineHeight`, and `\gothamFootlineDepth`. These variables are documented on page 35.)

\defbeamertemplate*{footline}{default/gotham} Template that is activate by default since this footline is relatively generic.

The following test files are used for this code: gotham-test-048.

```
3590 \defbeamertemplate*{footline}{default/gotham}{  
3591   % new line to adjust the footline position.  
3592   \vspace*{\gothamFootlineVOffset}  
3593   \begin{beamercolorbox}[  
3594     wd=\textwidth,  
3595     sep=0pt,  
3596     leftskip=3ex,  
3597     rightskip=3ex,
```

```

3598 ht={\gothamFootlineHeight},
3599 dp={\gothamFootlineDepth},
3600 ]{footline}
3601 \usebeamertemplate{page number in head/foot}
3602 \ifbeamertemplateempty{frame~footer}{
3603 %executed if empty
3604 \hfill \ \gotham@strut
3605 }{
3606 %<executed otherwise>
3607 \usebeamertemplate*{frame~footer}
3608 }
3609 \hspace{\gothamRightFooterPadding}
3610 {\usebeamertemplate{page~number~in~head/foot}}
3611 \hspace*{\gothamFootlineHRightOffset}
3612 \end{beamercolorbox}
3613 }
3614 \prop_put:Nnn \l__gotham_template_name_prop {footline/default} {gotham}

```

(End of definition for \defbeamertemplate*{footline}{default/gotham}. This function is documented on page ??.)

Footer

\gothamLeftFooterPadding
\gothamRightFooterPadding
\gothamFooterHOffset

Lengths used in footer template for positioning left right and bottom.

```

3615 \newlength{\gothamLeftFooterPadding}
3616 \newlength{\gothamRightFooterPadding}
3617 \newlength{\gothamFooterHOffset}
3618 \setlength{\gothamLeftFooterPadding}{2.0ex}
3619 \setlength{\gothamRightFooterPadding}{3.5ex}
3620 \setlength{\gothamFooterHOffset}{0pt}

```

(End of definition for \gothamLeftFooterPadding, \gothamRightFooterPadding, and \gothamFooterHOffset. These variables are documented on page 36.)

\defbeamertemplate{frame~footer}{none}

Footer template used when nothing is put as footer but it will create undesired results.

The following test files are used for this code: gotham-test-048.

```
3621 \defbeamertemplate{frame~footer}{none}{}
```

(End of definition for \defbeamertemplate{frame~footer}{none}. This function is documented on page ??.)

\defbeamertemplate{frame~footer}{empty}

Footer template used when nofooter option is given and it preserves spacing to have nice results.

The following test files are used for this code: gotham-test-048.

```
3622 \defbeamertemplate{frame~footer}{empty}{  
3623   \hspace{\gothamLeftFooterPadding}  
3624   \hfill  
3625   \gotham@strut  
3626   % decrease space between progress bar and footer  
3627   \vspace*{\gothamFooterHOffset}  
3628 }
```

(End of definition for \defbeamertemplate{frame~footer}{empty}. This function is documented on page ??.)

-]**\begin{frame}[nofooter]** Add a frame option **nofooter** to do not display an empty footer. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-048.

```
3629 % bool to trigger the add of nofooter in frame.  
3630 \newenvironment{nofooterenv}{  
3631   \setbeamertemplate{frame~footer}{empty}  
3632 }{}  
3633 \__gotham_add_beamerframe_key:n {nofooter}
```

(End of definition for \begin{frame}[nofooter]. This function is documented on page 36.)

- \l_gotham_defaultRotateFooter** Boolean variable to display the rotated footer by default (or not).

The following test files are used for this code: gotham-test-048.

```
3634 \bool_new:N \l_gotham_defaultRotateFooter  
3635 \bool_set_false:N \l_gotham_defaultRotateFooter  
3636 \bool_new:N \l_gotham_RotateFooter  
3637 \bool_set_false:N \l_gotham_RotateFooter  
3638 % At every new frame, reset the options to default (unless some options/keys are given)  
3639 \BeforeBeginEnvironment{frame}{  
3640   \bool_if:NTF \l_gotham_defaultRotateFooter {  
3641     \bool_set_true:N \l_gotham_RotateFooter  
3642   }% false  
3643   \bool_set_false:N \l_gotham_RotateFooter  
3644 }  
3645 }
```

(End of definition for \l_gotham_defaultRotateFooter. This function is documented on page 36.)

-]**\begin{frame}[rotateFooter]** Add a frame option **rotateFooter** to display a rotated footer. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-048.

```
3646 % bool to trigger
3647 % Capture new options/keys for frames
3648 \define@key{beamerframe}{rotateFooter}[true]{
3649   \bool_set_true:N \l_gotham_RotateFooter
3650 }
```

(End of definition for \begin{frame}[rotateFooter]. This function is documented on page 36.)

-]**\begin{frame}[noRotateFooter]** Add a frame option **noRotateFooter** to display a none-rotated footer. To do it, we must add a global boolean variable, capture the option at the begin of the frame and patch the end of the frame.

The following test files are used for this code: gotham-test-048.

```
3651 % Capture new options/keys for frames
3652 \define@key{beamerframe}{noRotateFooter}[true]{
3653   \bool_set_false:N \l_gotham_RotateFooter
3654 }
```

(End of definition for \begin{frame}[noRotateFooter]. This function is documented on page 36.)

- outer_key_interface** Controls the outer settings for sidebar canvas right and sidebar canvas left.

The following test files are used for this code: gotham-test-048.

```
3655 \keys_define:nn { gotham / outer }{
3656   % rotateFooter default
3657   rotateFooter~default .choice:,
3658   rotateFooter~default .usage:n = { general },
3659   rotateFooter~default .default:n = { false },
3660
3661   rotateFooter~default / true .code:n = { \bool_set_true:N \l_gotham_defaultRotateFooter },
3662   rotateFooter~default / on .code:n = { \bool_set_true:N \l_gotham_defaultRotateFooter },
3663   rotateFooter~default / enable .code:n = { \bool_set_true:N \l_gotham_defaultRotateFooter },
3664
3665   rotateFooter~default / false .code:n = { \bool_set_false:N \l_gotham_defaultRotateFooter },
3666   rotateFooter~default / off .code:n = { \bool_set_false:N \l_gotham_defaultRotateFooter },
3667   rotateFooter~default / disable .code:n = { \bool_set_false:N \l_gotham_defaultRotateFooter }
3668
3669   rotateFooter~default / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u }
```

```
3670 }
```

(End of definition for `outer key - interface`. This function is documented on page ??.)

`\gothamFootlineRuleLeftPadding`

```
\gothamFootlineRuleHeight  
\gothamFootlineRuleLength  
\gothamHposLeftRotFooter  
\gothamHposRightRotFooter  
\gothamVposLeftRotFooter  
\gothamVposRightRotFooter
```

Lengths used in footer template.

```
3671 \newlength{\gothamFootlineRuleLeftPadding}  
3672 \newlength{\gothamFootlineRuleHeight}  
3673 \newlength{\gothamFootlineRuleLength}  
3674  
3675 \setlength{\gothamFootlineRuleLeftPadding}{7mm}  
3676 \setlength{\gothamFootlineRuleHeight}{0.0pt}  
3677 % \setlength{\gothamFootlineRuleHeight}{0.5pt} % This is nice also but have a cleaner default  
3678 \setlength{\gothamFootlineRuleLength}{15mm}  
3679  
3680 % horizontal position (in picture env) for the rotated footer.  
3681 \newlength{\gothamHposLeftRotFooter}  
3682 \newlength{\gothamHposRightRotFooter}  
3683 \newlength{\gothamVposLeftRotFooter}  
3684 \newlength{\gothamVposRightRotFooter}  
3685  
3686 \setlength{\gothamHposLeftRotFooter}{-7pt}  
3687 \setlength{\gothamHposRightRotFooter}{2pt}  
3688 \setlength{\gothamVposLeftRotFooter}{15pt}  
3689 \setlength{\gothamVposRightRotFooter}{15pt}
```

(End of definition for `\gothamFootlineRuleLeftPadding` and others. These variables are documented on page ??.)

`\hlenRightRotFooter`

Temporary variables for the horizontal length of the rotated footer

```
\hlenLeftRotFooter  
3690 % Not used yet because I need to have a latex3 settowidth equivalent.  
3691 % I will maybe take inspiration from https://tex.stackexchange.com/questions/492367/does-exp  
3692 % \dim_new:N \l__gotham_HLen_rightRotFooter_dim  
3693 % \dim_new:N \l__gotham_HLen_leftRotFooter_dim  
3694 \newlength{\hlenRightRotFooter}  
3695 \newlength{\hlenLeftRotFooter}
```

(End of definition for `\hlenRightRotFooter` and `\hlenLeftRotFooter`. These variables are documented on page ??.)

`eamerTemplate{frame-footer}{default/gotham}`

Template for frame footer used by gotham, allowing a rotated footer.

The following test files are used for this code: `gotham-test-048`.

```
3696 \providecommand{\gothamHookFooter}{}  
156
```

```

3697 \defbeamertemplate{frame~footer}{default/gotham}{
3698   %% Add a ruler but without affecting the dimensions of the footnote
3699   \vbox to 0pt{
3700     % Vertical stretch to ensure proper spacing
3701     \vss
3702     \hbox to 0pt{
3703       \hspace*{\gothamFootlineRuleLeftPadding}
3704       % \usebeamercolor{frametitle}
3705       % \color{frametitle.bg}
3706       \usebeamercolor{footlineRule}
3707       \color{footlineRule.fg}
3708       \rule{\gothamFootlineRuleLength}{\gothamFootlineRuleHeight}
3709       \vspace*{
3710         \dimexpr \gothamFootlineHeight -0.25em\relax
3711       }
3712       % Horizontal stretch to ensure proper spacing
3713       \hss
3714     }
3715   }
3716   %% Add Hook
3717   \gothamHookFooter{}
3718   %% Add short date
3719   \hspace{\gothamLeftFooterPadding}
3720   \settowidth{\hlenLeftRotFooter}{\hspace{-\gothamLeftFooterPadding}}
3721   \addtolength{\hlenLeftRotFooter}{\gothamHposLeftRotFooter}
3722   % \ifbool{rotateFooter}{
3723     \bool_if:NTF \l_gotham_RotateFooter {
3724       % rotateFooter true
3725       \begin{picture}(0,0)(0,0)
3726         \put(\hlenLeftRotFooter,\gothamVposLeftRotFooter){\rotatebox{90}{\insertshortdate}}
3727       \end{picture}
3728     }{
3729       % rotateFooter false
3730       \insertshortdate
3731     }
3732     \hfill \
3733   %% Add short title
3734   \hfill \insertshorttitle
3735   % make sure that the vertical space is constant: strut.
3736   \gotham@strut
3737   \hfill \
3738   \hfill \
3739   %% Add short author

```

```

3740 \bool_if:NTF \l_gotham_RotateFooter {
3741   % rotateFooter true
3742   \settowidth{\hlenRightRotFooter}{\hspace{\gothamRightFooterPadding}\usebeamertemplate[page
3743   \addtolength{\hlenRightRotFooter}{\gothamHposRightRotFooter}
3744   \begin{picture}(0,0)(0,0)
3745     \put(\hlenRightRotFooter,\gothamVposRightRotFooter){\rotatebox{90}{\insertshortauthor}}
3746   \end{picture}
3747 }
3748 % rotateFooter false
3749 \insertshortauthor
3750 }
3751 %%% Decrease space between progress bar and footer
3752 \vspace*{-\gothamFooterHOffset}
3753 }
3754 \prop_put:Nnn \l__gotham_template_name_prop {frame~footer/default} {gotham}

```

(End of definition for `\defbeamertemplate{frame~footer}{default/gotham}`. This function is documented on page ??.)

`outer~key~-~interface` Controls the outer settings for footer template.

The following test files are used for this code: gotham-test-048.

```

3755 \keys_define:nn { gotham / outer }{
3756   % footer template
3757   footer-template .usage:n = { general },
3758   footer-template .default:n = { gotham },
3759   footer-template .code:n = {
3760     \__gotham_set_prop_template:nn{frame~footer/default}{#1}
3761     \setbeamertemplate{frame~footer}[
3762       default/\prop_item:Nn \l__gotham_template_name_prop {frame~footer/default}
3763     ]
3764   }
3765 }

```

(End of definition for `outer key - interface`. This function is documented on page ??.)

Numbering

`\inserttotalframenumber` We defined the number of total frame, if not defined or equal to 0 because of the first compilation, we set it to avoid arithmetical errors

The following test files are used for this code: gotham-test-046.

```

3766 %
3767 \def\inserttotalframenumber{100}

```

(End of definition for `\inserttotalframenumber`. This function is documented on page ??.)

`\mertemplate{page-number-in-head/foot}{none}` Template to do not numbering the current frame.

The following test files are used for this code: gotham-test-048.

```
3768 \defbeamertemplate{page-number-in-head/foot}{none}{ }
```

(End of definition for `\defbeamertemplate{page-number-in-head/foot}{none}`. This function is documented on page ??.)

`\gothamCircleNumberingVshift` Length used in `raisebox` and `hspace` in `circle` frame numbering.

`\gothamCircleNumberingHshift`

```
3769 \newlength{\gothamCircleNumberingVshift}
3770 \newlength{\gothamCircleNumberingHshift}
3771 \setlength{\gothamCircleNumberingVshift}{1.4mm}
3772 \setlength{\gothamCircleNumberingHshift}{2.6mm}
```

(End of definition for `\gothamCircleNumberingVshift` and `\gothamCircleNumberingHshift`. These variables are documented on page 37.)

`\rtemplate{page-number-in-head/foot}{circle}` Template to add, in a circle, the number of the current frame over (slash) the total number of frames.

The following test files are used for this code: gotham-test-048.

```
3773 \defbeamertemplate{page-number-in-head/foot}{circle}{%
3774   % horizontal space between the circle and the right part of the footer (email).
3775   \hspace{+2em}
3776   % \raisebox{lift}[height][depth]{text} => lift here = vertical space between the bottom of
3777   \raisebox{\gothamCircleNumberingVshift}[0pt][0pt]{%
3778     \begin{tikzpicture}[remember picture, overlay]
3779       \coordinate (circleCenter);
3780
3781       \usebeamercolor{frametitle}
3782
3783       \draw[fill, color=frametitle.bg] (circleCenter) circle (6mm);
3784       \draw[fill, color=frametitle.fg] (circleCenter) circle (5mm);
3785       \node[color=frametitle.bg] at (circleCenter)
3786         {\small$^{\{\insertframenumber}\negmedspace/\negthinspace\sb{\inserttotalframenumber}\}}$};
3787     ;
3788   \end{tikzpicture}
3789   % horizontal space between the right border of the page and the center of the circle.
3790   \hspace{\gothamCircleNumberingHshift}
3791 }
3792 }
```

(End of definition for \defbeamertemplate{page~number-in~head/foot}{circle}. This function is documented on page ??.)

outer_key_interface Controls the outer settings for frame numbering.

The following test files are used for this code: gotham-test-048.

```
3793 \keys_define:nn { gotham / outer }{
3794   % numbering
3795   numbering .choice:,
3796   numbering .usage:n = { general },
3797   numbering .default:n = { none },
3798
3799   % \__gotham_set_template:nn{title~page}{#1}
3800   numbering / none .code:n = { \setbeamertemplate{page~number~in~head/foot}[none] },
3801   numbering / framenumber .code:n = { \setbeamertemplate{page~number~in~head/foot}[framenumber]
3802   numbering / totalframenumber .code:n = { \setbeamertemplate{page~number~in~head/foot}[totalframenumber]
3803   numbering / appendixframenumber .code:n = { \setbeamertemplate{page~number~in~head/foot}[appendixframenumber]
3804   numbering / pagenumber .code:n = { \setbeamertemplate{page~number~in~head/foot}[pagnumber]
3805   numbering / totalpagnumber .code:n = { \setbeamertemplate{page~number~in~head/foot}[totalpagnumber]
3806   numbering / circle .code:n = { \setbeamertemplate{page~number~in~head/foot}[circle] },
3807
3808   numbering / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~unknown~for~
3809 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

MiniFrames & Progress bar

MiniFrames

plate{section-in-head/foot}{default/beamer} Template control how the section appears by default when sections are add to the headline or footline.

The following test files are used for this code: gotham-test-048.

```
3810 \defbeamertemplate{section-in-head/foot}{default/beamer}{
3811   \insertsectionhead
3812 }
3813 \defbeamertemplate{section-in-head/foot~shaded}{default/beamer}{
3814   \color{fg!50!bg}\usebeamertemplate{section-in-head/foot}
3815 }
3816
3817 % \defbeamertemplate{includeLogo}{default/gotham-square}{
3818 \prop_put:Nnn \l__gotham_template_name_prop {section-in-head/foot~shaded/default} {beamer}
3819 % \defbeamertemplate{includeLogo}{default/gotham-square}{
```

```
3820 \prop_put:Nnn \l__gotham_template_name_prop {section~in~head/foot/default} {beamer}
```

(End of definition for \defbeamertemplate{section-in-head/foot}{default/beamer}. This function is documented on page ??.)

Template for section and subsection in headline.

The following test files are used for this code: gotham-test-048.

```
3821 \defbeamertemplate{section-in-head/foot}{default/gotham~secSubsec}{  
3822   \insertsectionhead  
3823   \ifx\insertsubsection\empty\else  
3824     \ifdefempty{\subsecname}{\relax}{  
3825       \textbar\ \insertsubsectionhead  
3826     }  
3827   \fi  
3828 }  
3829 \defbeamertemplate{section-in-head/foot~shaded}{default/gotham~secSubsec}{  
3830   \insertsectionhead  
3831 }
```

(End of definition for \defbeamertemplate{section-in-head/foot}{default/gotham~secSubsec}. This function is documented on page ??.)

Empty template for section in headline, compensating the height of a line.

The following test files are used for this code: gotham-test-048.

```
3832 \defbeamertemplate{section-in-head/foot}{default/empty}{  
3833   \vspace{3.875ex}  
3834 }  
3835 \defbeamertemplate{section-in-head/foot~shaded}{default/empty}{  
3836   \vspace{3.875ex}  
3837 }
```

(End of definition for \defbeamertemplate{section-in-head/foot}{default/empty}. This function is documented on page ??.)

\gotham@temp@heightFrametitle Temporary length variables to compute the height of the frametitle and the height of the paper minus the frametitle.

```
3838 \newlength{\gotham@temp@heightFrametitle}  
3839 \newlength{\gotham@temp@PaperheightFrametitle}
```

(End of definition for \gotham@temp@heightFrametitle and \gotham@temp@PaperheightFrametitle. These variables are documented on page ??.)

d/foot, left, right}{gotham-miniframes-theme}

Template to insert the navigation bar (using miniframes) that can be added to headline (or footline) left sidebar or righ sidebar.

The following test files are used for this code: gotham-test-048.

```

3840 \defbeamertemplate*{mini~nav~progress~head/foot}{gotham~miniframes~theme}
3841 {
3842   %,ht=1.75ex,dp=2.75ex
3843   \begin{beamercolorbox}[ignorebg]{section~in~head/foot}
3844     \hfuzz=\paperwidth
3845     \insertnavigation{\paperwidth}
3846     % \dohead
3847     \vspace{0.05cm}
3848   \end{beamercolorbox}
3849 }
3850 \defbeamertemplate*{mini~nav~progress~left}{gotham~miniframes~theme}
3851 {
3852   \settoheight{\gotham@temp@heightFrametitle}{\gotham@strut}
3853   \addtolength{\gotham@temp@heightFrametitle}{\gothamFrametitleToppading+\gothamFrametitleBot}
3854
3855   \setlength{\gotham@temp@PaperheightFrametitle}{\paperheight-\gotham@temp@heightFrametitle-\voffset}
3856
3857   \vspace{-0.6\paperheight}
3858   \rotatebox{90}{
3859     %,ht=1.75ex,dp=2.75ex
3860     \begin{beamercolorbox}[ignorebg]{section~in~head/foot}
3861       \hfuzz=\gotham@temp@PaperheightFrametitle
3862       \insertnavigation{\gotham@temp@PaperheightFrametitle}
3863       % \dohead
3864       % \vspace{0.05cm}
3865     \end{beamercolorbox}
3866   }
3867 }
3868 \defbeamertemplate*{mini~nav~progress~right}{gotham~miniframes~theme}
3869 {
3870   \settoheight{\gotham@temp@heightFrametitle}{\gotham@strut}
3871   \addtolength{\gotham@temp@heightFrametitle}{\gothamFrametitleToppading+\gothamFrametitleBot}
3872
3873   \setlength{\gotham@temp@PaperheightFrametitle}{\paperheight-\gotham@temp@heightFrametitle-\voffset}
3874
3875   \vspace{\gotham@temp@heightFrametitle}
3876   \hspace{-2.3em}
3877   \rotatebox{-90}{
3878     %,ht=1.75ex,dp=2.75ex

```

```

3879 \begin{beamercolorbox}[ignorebg]{section~in~head/foot}
3880   \hfuzz=\gotham@temp@PaperheightFrametitle
3881   \insertnavigation{\gotham@temp@PaperheightFrametitle}
3882   % \dohead
3883   % \vspace{0.05cm}
3884 \end{beamercolorbox}
3885 }
3886 }

```

(End of definition for \defbeamertemplate{mini~nav~progress~head/foot left right}{gotham~miniframes~theme}.
This function is documented on page ??.)*

Select the bullets shape

\defbeamertemplate{mini-frame}{gotham-box} Template to add a new shape for miniframes gotham box.

The following test files are used for this code: gotham-test-048.

```

3887 \defbeamertemplate{mini~frame}{gotham~box}
3888 {
3889   \begin{pgfpicture}{0pt}{0pt}{.1cm}{.1cm}
3890     \pgfpathrectangle{\pgfpointorigin}{\pgfpoint{0.1cm}{0.1cm}}
3891     \pgfusepath{fill,stroke}
3892   \end{pgfpicture}
3893 }[action]{
3894   \setbeamersize{mini~frame~size=.14cm, mini~frame~offset=.05cm}
3895 }
3896 %
3897 \defbeamertemplate{mini~frame~in~current~subsection}{gotham~box}
3898 {
3899   \begin{pgfpicture}{0pt}{0pt}{.1cm}{.1cm}
3900     \pgfpathrectangle{\pgfpointorigin}{\pgfpoint{0.1cm}{0.1cm}}
3901     \pgfusepath{stroke}
3902   \end{pgfpicture}
3903 }

```

(End of definition for \defbeamertemplate{mini-frame}{gotham-box}. This function is documented on page ??.)

\defbeamertemplate{mini-frame}{gotham-minibox} Template to add a new shape for miniframes gotham minibox.

The following test files are used for this code: gotham-test-048.

```

3904 \defbeamertemplate{mini~frame}{gotham~minibox}
3905 {
3906   \begin{pgfpicture}{0pt}{0pt}{.05cm}{.05cm}

```

```

3907  \pgfpathrectangle{\pgfpointorigin}{\pgfpoint{0.05cm}{0.05cm}}
3908  \pgfusepath{fill,stroke}
3909  \end{pgfpicture}
3910 }[action]{
3911 \setbeamersize{mini-frame-size=.08cm, mini-frame-offset=.05cm}
3912 }
3913 %
3914 \defbeamertemplate{mini-frame-in-current-subsection}{gotham-minibox}
3915 {
3916 \begin{pgfpicture}[0pt]{0pt}{.05cm}{.05cm}
3917 \pgfpathrectangle{\pgfpointorigin}{\pgfpoint{0.05cm}{0.05cm}}
3918 \pgfusepath{stroke}
3919 \end{pgfpicture}
3920 }

```

(End of definition for `\defbeamertemplate{mini-frame}{gotham-minibox}`. This function is documented on page ??.)

`amertemplate{mini-frame}{gotham-minibullet}` Template to add a new shape for miniframes `gotham minibullet`.

The following test files are used for this code: `gotham-test-048`.

```

3921 \defbeamertemplate{mini-frame}{gotham-minibullet}
3922 {
3923 \beamer@xelatex@fixminiframes
3924 \begin{pgfpicture}[0pt]{0pt}{0.05cm}{0.05cm}
3925 \pgfpathcircle{\pgfpoint{0.03cm}{0.03cm}}{0.03cm}
3926 \pgfusepath{fill,stroke}
3927 \end{pgfpicture}
3928 }[action]{
3929 \setbeamersize{mini-frame-size=.09cm, mini-frame-offset=.05cm}
3930 }
3931 %
3932 \defbeamertemplate{mini-frame-in-current-subsection}{gotham-minibullet}
3933 {
3934 \beamer@xelatex@fixminiframes
3935 \begin{pgfpicture}[0pt]{0pt}{0.05cm}{0.05cm}
3936 \pgfpathcircle{\pgfpoint{0.03cm}{0.03cm}}{0.03cm}
3937 \pgfusepath{stroke}
3938 \end{pgfpicture}
3939 }

```

(End of definition for `\defbeamertemplate{mini-frame}{gotham-minibullet}`. This function is documented on page ??.)

`outer_key_interface` Controls the outer settings for mini frames shape template.

The following test files are used for this code: gotham-test-048.

```
3940 \keys_define:nn { gotham / outer }{
3941   %% mini~frames~shape
3942   % mini~frames~shape .choice:,
3943   mini~frames~shape .usage:n = { general },
3944   mini~frames~shape .default:n = { gotham~minibullet },
3945   % \__gotham_set_template:nn{title~page}{#1}
3946   mini~frames~shape .code:n = {
3947     % \__gotham_set_template:nn{mini~frames}{#1}% This can not work since this is an alias, so
3948     \setbeamertemplate{mini~frames}[#1]
3949   },
3950   % mini~frames~shape / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~un
3951 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

`\defbeamertemplate*{miniframe~home}` Template to adapt Beamer to the internal modification brought by Gotham: differentiation between slide to come and those done, idem for section, subsection...

The following test files are used for this code: gotham-test-048.

```
3952 \defbeamertemplate*{miniframe~home}{beamer}{
3953   % $\equiv$%
3954 }
3955 \defbeamertemplate*{miniframe~current~slide}{beamer}{
3956   \usebeamertemplate{mini~frame}
3957 }
3958 \defbeamertemplate*{miniframe~done~current~section}{beamer}{
3959   \usebeamertemplate{mini~frame~in~current~subsection}
3960 }
3961 \defbeamertemplate*{miniframe~todo~current~section}{beamer}{
3962   \usebeamertemplate{mini~frame~in~current~subsection}
3963 }
3964 \defbeamertemplate*{miniframe~done~other~section}{beamer}{
3965   \usebeamertemplate{mini~frame~in~other~subsection}
3966 }
3967 \defbeamertemplate*{miniframe~todo~other~section}{beamer}{
3968   \usebeamertemplate{mini~frame~in~other~subsection}
3969 }
3970 % Templates about should appear sectioning in mini frame.
3971 % \defbeamertemplate*{miniframe~part}{beamer}{}
3972 \defbeamertemplate*{miniframe~section~current}{beamer}{}
```

```

3973 \defbeamertemplate*{miniframe~section~done}{beamer}(){}
3974 \defbeamertemplate*{miniframe~section~todo}{beamer}(){}
3975 \defbeamertemplate*{miniframe~subsection~current}{beamer}(){}
3976 \defbeamertemplate*{miniframe~subsection~todo}{beamer}(){}
3977 \defbeamertemplate*{miniframe~subsection~done}{beamer}(){}
3978 % \defbeamertemplate*{miniframe~subsubsection}{beamer}(){}
3979 \defbeamertemplate*{miniframe~section~done~in~other~section}{default}[1][50]
3980 {
3981   \color{fg!#1!bg}\usebeamertemplate{miniframe~section~done}
3982 }
3983 \defbeamertemplate*{miniframe~section~todo~in~other~section}{default}[1][50]
3984 {
3985   \color{fg!#1!bg}\usebeamertemplate{miniframe~section~todo}
3986 }
3987 \defbeamertemplate*{miniframe~subsection~done~in~other~section}{default}[1][50]
3988 {
3989   \color{fg!#1!bg}\usebeamertemplate{miniframe~subsection~done}
3990 }
3991 \defbeamertemplate*{miniframe~subsection~todo~in~other~section}{default}[1][50]
3992 {
3993   \color{fg!#1!bg}\usebeamertemplate{miniframe~subsection~todo}
3994 }

```

(End of definition for `\defbeamertemplate*{miniframe~home}`. This function is documented on page ??.)

`beamertemplate{miniframe~home}{gotham~mini}` Templates for miniframes using a Gotham style inspired by a miniaturization than the one from Beamer.

The following test files are used for this code: `gotham-test-048`.

```

3995 \defbeamertemplate{miniframe~home}{gotham~mini}{
3996   \resizebox{0.85\beamer@boxsize}{\beamer@boxsize}{$\equiv$}
3997   % \scalebox{0.5}[0.95]{$\equiv$}
3998 }
3999 \defbeamertemplate{miniframe~current~slide}{gotham~mini}{
4000   \usebeamercolor[fg]{alerted-text}
4001   \usebeamertemplate{mini~frame}
4002 }
4003 \defbeamertemplate{miniframe~done~current~section}{gotham~mini}{
4004   \usebeamertemplate{mini~frame}
4005 }
4006 \defbeamertemplate{miniframe~todo~current~section}{gotham~mini}{
4007   \usebeamertemplate{mini~frame~in~current~subsection}
4008 }

```

```

4009 \defbeamertemplate{miniframe~done~other~section}{gotham~mini}[1][50]{
4010   \color{fg!#1!bg}\usebeamertemplate{mini~frame}
4011 }
4012 \defbeamertemplate{miniframe~todo~other~section}{gotham~mini}[1][50]{
4013   \color{fg!#1!bg}\usebeamertemplate{mini~frame~in~other~subsection}
4014 }
4015 % Templates about should appear sectioning in mini frame.
4016 % \defbeamertemplate{miniframe~part}{gotham~mini}[1][]{
4017 %   p
4018 %
4019 \defbeamertemplate{miniframe~section~current}{gotham~mini}{
4020   \fontsize{3pt}{0pt}\selectfont
4021   % \color{blue}
4022   \tl_use:N \l__gotham_minif_tmpa_tl
4023   \hspace{1.pt}
4024 }
4025 \defbeamertemplate{miniframe~section~done}{gotham~mini}{
4026   \fontsize{3pt}{0pt}\selectfont
4027   % \color{green}
4028   \tl_use:N \l__gotham_minif_tmpa_tl
4029   \hspace{1.pt}
4030 }
4031 \defbeamertemplate{miniframe~section~todo}{gotham~mini}{
4032   \fontsize{3pt}{0pt}\selectfont
4033   % \color{red}
4034   \tl_use:N \l__gotham_minif_tmpa_tl
4035   \hspace{1.pt}
4036 }
4037 \defbeamertemplate{miniframe~subsection~current}{gotham~mini}{
4038   \usebeamercolor[fg]{alerted-text}
4039   \hspace{-0.15pt}
4040   \resizebox{\beamer@boxsize}{!}{\hspace{-0.75pt}$\blacklozenge$}
4041 }
4042 \defbeamertemplate{miniframe~subsection~todo}{gotham~mini}{
4043   \hspace{-0.15pt}
4044   \resizebox{\beamer@boxsize}{!}{\hspace{-0.75pt}$\lozenge$}
4045 }
4046 \defbeamertemplate{miniframe~subsection~done}{gotham~mini}{
4047   \hspace{-0.15pt}
4048   \resizebox{\beamer@boxsize}{!}{\hspace{-0.75pt}$\blacklozenge$}
4049 }
4050 % \defbeamertemplate{miniframe~subsubsection}{gotham~mini}%
4051 %   d

```

```
4052 % }
```

(End of definition for \defbeamertemplate{miniframe-home}{gotham-mini}. This function is documented on page ??.)

beamertemplate{miniframe-home}{gotham-nano} Template for Gotham mini frame style using even less space.

The following test files are used for this code: gotham-test-048.

```
4053 \defbeamertemplate{miniframe~home}{gotham~nano}{
4054   % \resizerbox{\beamer@boxsize}{!}{\$\equiv}
4055   \scalebox{0.5}[0.95]{\$\equiv}
4056 }
4057 \defbeamertemplate{miniframe~current~slide}{gotham~nano}{
4058   o
4059 }
4060 \defbeamertemplate{miniframe~done~current~section}{gotham~nano}{
4061   x
4062 }
4063 \defbeamertemplate{miniframe~todo~current~section}{gotham~nano}{
4064   $\cdot$%
4065 }
4066 \defbeamertemplate{miniframe~done~other~section}{gotham~nano}{
4067   x
4068 }
4069 \defbeamertemplate{miniframe~todo~other~section}{gotham~nano}{
4070   $\cdot$%
4071 }
4072 % Templates about should appear sectioning in mini frame.
4073 % \defbeamertemplate{miniframe~part}{gotham~nano}[1][]{%
4074 %   p
4075 % }
4076 \defbeamertemplate{miniframe~section~current}{gotham~nano}{
4077   \tl_use:N \l__gotham_minif_tma_tl
4078 }
4079 \defbeamertemplate{miniframe~section~done}{gotham~nano}{
4080   \tl_use:N \l__gotham_minif_tma_tl
4081 }
4082 \defbeamertemplate{miniframe~section~todo}{gotham~nano}{
4083   \tl_use:N \l__gotham_minif_tma_tl
4084 }
4085 \defbeamertemplate{miniframe~subsection~current}{gotham~nano}{
4086   \usebeamercolor[fg]{alerted-text}\diamond%
4087 }
4088 \defbeamertemplate{miniframe~subsection~todo}{gotham~nano}{
```

```

4089   \$\diamondond$  

4090 }  

4091 \defbeamertemplate{miniframe~subsection~done}{gotham~nano} {  

4092   \$\diamondond$  

4093 }

```

(End of definition for \defbeamertemplate{miniframe~home}{gotham~nano}. This function is documented on page ??.)

defbeamertemplateparent{mini-frames~bundle} Define a parent template to set the 6 templates at once.

The following test files are used for this code: gotham-test-048.

```

4094 \defbeamertemplateparent{mini~frames~bundle}  

4095 { miniframe~home, miniframe~current~slide,  

4096   miniframe~done~current~section, miniframe~todo~current~section, miniframe~done~other~section,  

4097   miniframe~section~current, miniframe~section~done, miniframe~section~todo,  

4098   miniframe~subsection~current, miniframe~subsection~done, miniframe~subsection~todo,  

4099 }{}  

4100 \%setbeamertemplate{mini~frames~bundle}[gotham~mini]@[beamer]@[gotham~nano]%

```

(End of definition for \defbeamertemplateparent{mini~frames~bundle}. This function is documented on page ??.)

outer_key_interface Controls the outer settings for mini frames bundle template.

The following test files are used for this code: gotham-test-050.

```

4101 \keys_define:nn { gotham / outer }{  

4102   %% mini~frames~bundle  

4103   % mini~frames~bundle .choice:,  

4104   mini~frames~bundle .usage:n = { general },  

4105   mini~frames~bundle .default:n = { gotham~mini },  

4106   % \__gotham_set_template:nn{title~page}{#1}  

4107   mini~frames~bundle .code:n = {  

4108     % \__gotham_set_template:nn{mini~frames}{#1}% This can not work since this is an alias, so  

4109     \%setbeamertemplate{mini~frames~bundle}[]{#1}  

4110   },  

4111   % mini~frames~bundle / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~un  

4112 }

```

(End of definition for outer key - interface. This function is documented on page ??.)

MiniFrames Navigation

outer_key_interface Controls the outer settings for mini frames compress template.

The following test files are used for this code: gotham-test-050.

```
4113 \keys_define:nn { gotham / outer }{
4114   % mini-frames-compress default
4115   mini-frames-compress .choice:,,
4116   mini-frames-compress .usage:n = { general },
4117   mini-frames-compress .default:n = { true },
4118
4119   mini-frames-compress / true .code:n = { \beamer@compressstrue },
4120   mini-frames-compress / on .code:n = { \beamer@compressstrue },
4121   mini-frames-compress / enable .code:n = { \beamer@compressstrue },
4122
4123   mini-frames-compress / false .code:n = { \beamer@compressfalse },
4124   mini-frames-compress / off .code:n = { \beamer@compressfalse },
4125   mini-frames-compress / disable .code:n = { \beamer@compressfalse },
4126
4127   mini-frames-compress / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u
4128 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

\l__gotham_minif_tmpa_tl Temporary variables used for the store dimension of the miniframe subsection, check if the last section treated and the pass the value of the section to the section template.

\gotham@temp@lastSec

```
4129 \newlength{\gotham@temp@MiniframeSubsecDim}
4130 \newlength{\gotham@temp@MiniframeSecDim}
4131 \def\gotham@temp@lastSec{-1}
4132 \tl_new:N \l__gotham_minif_tmpa_tl
4133 \tl_new:N \l__gotham_minif_tmpb_tl
```

(End of definition for \l__gotham_minif_tmpa_tl, \gotham@temp@MiniframeSubsecDim, and \gotham@temp@lastSec. These variables are documented on page ??.)

```
\renewcommand{\slideentry}{
```

Redefinition of the slideentry command from Beamer in order to add home page symbol, section symbol, subsection symbol to come and done.

The following test files are used for this code: gotham-test-048.

```

4134 % definition from Beamerbasenavigation.sty
4135 % \def\slideentry#1#2#3#4#5#6{%
4136 \renewcommand{\slideentry}[6]{%
4137   %section number, subsection number, slide number, first/last frame, page number, part num
4138 \ifnum#6=1\c@part\ifnum#3>0\ifnum#6=\c@part\ifnum#1>0\ifnum#3>0 MODIF
4139 \ifbeamer@compress%
4140   \advance\beamer@xpos by1\relax%
4141 \else%
4142   \ifnum#2=0%
4143     \beamer@ypos@offset=1\relax%
4144   \fi%
4145   \beamer@xpos=#3\relax%
4146   \beamer@ypos=#2\relax%
4147   \advance\beamer@ypos by \beamer@ypos@offset\relax%
4148 \fi%
4149 %% Add section number and subsection symbol to miniframes.
4150 %% MODIF below, inspired from https://tex.stackexchange.com/questions/722523
4151 \ifnum#3=1%\c@subsectionslide=#3 % if =1, so it has been reset => new section or subsecti
4152 \ifnum#1>0\ifnum#2<2% => there no subsection in this section.
4153   \ifnum\gotham@temp@lastSec=#1%
4154     % this means, that we already went through: there no subsec, then the first subsec has
4155   \else%
4156     \tl_set:Nn \l__gotham_minif_tlp{#1}
4157     \settowidth{\gotham@temp@MiniframeSecDim}{\usebeamertemplate{miniframe~section~current}}
4158     % \addtolength{\gotham@temp@MiniframeSecDim}{1.5pt}
4159     \hbox to \Opt{%
4160       \beamer@tempdim=-\beamer@vboxoffset%
4161       \advance\beamer@tempdim by-\beamer@boxsize%
4162       \multiply\beamer@tempdim by\beamer@ypos%
4163       \advance\beamer@tempdim by -.05cm%
4164       \raise\beamer@tempdim\hbox{%
4165         \beamer@tempdim=\beamer@boxsize%
4166         \multiply\beamer@tempdim by\beamer@xpos%
4167         \advance\beamer@tempdim by -\beamer@boxsize%
4168         \advance\beamer@tempdim by -\gotham@temp@MiniframeSecDim% NEW
4169         \advance\beamer@tempdim by 1pt%
4170         \kern\beamer@tempdim%
4171         \global\beamer@section@min@dim\beamer@tempdim%
4172         \hbox{\beamer@link{#4}{%
4173           % \usebeamertemplate{miniframe~section}%
4174           % if not first page then check if it is the current section.
4175           \ifnum\c@section=#1%
4176             % check if it is the current slide
4177             \ifnum\c@subsectionslide=#3%
4178               \usebeamertemplate{miniframe~section~current}
4179             \else%

```

`gothamZerosectionframes` Boolean variable to flag if they are frame in a zeroth section.

```
4354 \providebool{gothamZerosectionframes}  
4355 \boolfalse{gothamZerosectionframes}
```

(End of definition for `gothamZerosectionframes`. This variable is documented on page 38.)

`\insertnavigation` Patches for `\insertnavigation` and `\sectionentry` to be able to adapt with spreading
`\sectionentry` values.

The following test files are used for this code: `gotham-test-048`.

```
4356 \providecommand{\gothamInsertNavlength}{  
4357 % spreading by default  
4358 \ifbool{gothamZerosectionframes}{  
4359 %true  
4360 % spreading  
4361 \hskip-0.5ex~plus~1fill  
4362 }{  
4363 %false  
4364 \hskip-1.875ex~plus~1fill  
4365 }%  
4366 }  
4367 \providecommand{\gothamPatchInsertNav}{  
4368 % Don't patch for now  
4369 \box\beamer@sectionbox\hfil\hskip.3cm  
4370 }  
4371 \providecommand{\gothamPatchSectionentry}{  
4372 % Don't patch for now  
4373 \hskip1.875ex~plus~1fill  
4374 }  
4375 \providecommand{\gothamPatchSectionbox}{  
4376 % Don't patch for now  
4377 \ht\beamer@sectionbox=1.875ex  
4378 \dp\beamer@sectionbox=0.75ex  
4379 }  
4380 \ExplSyntaxOff  
4381 % To let the 0-th section appear.  
4382 \patchcmd{\insertnavigation}{\hskip-1.875ex plus~1fill}{%  
4383 \ifnum\value{section}=0%  
4384 \ifnum\value{framenumber}>0%  
4385 \hskip-0ex%  
4386 \global\booltrue{gothamZerosectionframes}%  
4387 \fi\fi%  
4388 \gothamInsertNavlength%
```

```

4389 }{}{}
4390 %% Remove hfill between sections => flush right bullet bar, if not corrected.
4391 \patchcmd{\sectionentry}{\hspace{1.875ex plus 1fill}}{\gothamPatchSectionentry}{}{}
4392 %% Centering the bullet bar
4393 \patchcmd{\insertnavigation}{\boxbeamer@sectionbox\hfil\hspace{3cm}}{\gothamPatchInsertNav}{}{}
4394 % Patch size of sectionbox
4395 \patchcmd{\insertnavigation}{\ht\beamer@sectionbox=1.875ex%}
4396 \dp\beamer@sectionbox=0.75ex%
4397 }{
4398 \gothamPatchSectionbox
4399 }{}{}
4400 \patchcmd{\sectionentry}{\ht\beamer@sectionbox=1.875ex%}
4401 \dp\beamer@sectionbox=0.75ex%
4402 }{
4403 \gothamPatchSectionbox
4404 }{}{}
4405 \ExplSyntaxOn

```

(End of definition for \insertnavigation and \sectionentry. These functions are documented on page ??.)

`outer_key-interface` Controls the outer settings for mini frames navigation spreading.

The following test files are used for this code: gotham-test-051.

```

4406 \keys_define:nn { gotham / outer }{
4407   % mini-frames~nav-spreading default
4408   mini-frames~nav-spreading .choice:,
4409   mini-frames~nav-spreading .usage:n = { general },
4410   mini-frames~nav-spreading .default:n = { spreading },
4411
4412   mini-frames~nav-spreading / spreading .code:n = {
4413     %
4414     \renewcommand{\gothamInsertNavlength}{%
4415       \ifbool{gothamZerosectionframes}{%
4416         %true
4417         % spreading
4418         \hspace{-0.5ex}
4419       }{%
4420         %false
4421         \hspace{-1.875ex plus -1fill}
4422       }%
4423     }
4424   % No other patch needed, but renewcommand if it has been modified previously.
4425   \renewcommand{\gothamPatchInsertNav}{%

```

```

4426      % Don't patch for now
4427      \box\beamer@sectionbox\hfil\hskip.3cm
4428  }
4429  \renewcommand{\gothamPatchSectionentry}{%
4430      % Don't patch for now
4431      \hskip1.875ex plus~1fill
4432  }
4433 },
4434 mini~frames~nav~spreading / centering .code:n = {
4435 %
4436 \renewcommand{\gothamInsertNavlength}{%
4437 \ifbool{gothamZerosectionframes}{%
4438     %true
4439     % centering +patch sectionenty +patch insertnav @sectionbox
4440     \hskip-0.5ex plus~1fill
4441 }{%
4442     %false
4443     % \patchcmd{\insertnavigation}{\hskip-1.875ex plus-1fill}{\hfill}{}{}%
4444     \hfill
4445 }%
4446 }
4447 % Centering the bullet bar
4448 % \patchcmd{\insertnavigation}{\box\beamer@sectionbox\hfil\hskip.3cm}{\box\beamer@sectionbox\hfil\hskip.3cm}
4449 \renewcommand{\gothamPatchInsertNav}{%
4450     \box\beamer@sectionbox\hfill\hskip.3cm
4451 }%
4452 %% Remove hfill between sections => flush right bullet bar, if not corrected.
4453 % \patchcmd{\sectionentry}{\hskip1.875ex plus 1fill}{\hskip 3.5ex}{}{}%
4454 \renewcommand{\gothamPatchSectionentry}{%
4455     \hskip~3.5ex
4456 }
4457 },
4458 mini~frames~nav~spreading / left .code:n = {
4459 %
4460 \renewcommand{\gothamInsertNavlength}{%
4461 \ifbool{gothamZerosectionframes}{%
4462     %true
4463     % flush left +patch sectionenty
4464     \hskip-0.5ex
4465 }{%
4466     %false
4467     % no patch
4468     \hskip-1.875ex plus-1fill

```

```

4469     }%
4470   }
4471   % Centering the bullet bar : NO
4472   % no patch
4473   \renewcommand{\gothamPatchInsertNav}{%
4474     \box\beamer@sectionbox\hfil\hskip.3cm
4475   }
4476   %% Remove hfill between sections => flush right bullet bar, if not corrected.
4477   % \patchcmd{\sectionentry}{\hskip1.875ex plus 1fill}{\hskip 3.5ex}{}{%
4478   \renewcommand{\gothamPatchSectionentry}{%
4479     \hskip~3.5ex
4480   }
4481 },
4482   mini~frames~nav~spreading / right .code:n = {
4483   %
4484   \renewcommand{\gothamInsertNavlength}{%
4485     \ifbool{gothamZeroSectionFrames}{%
4486       %true
4487       % flush right +patch sectionenty
4488       \hskip-0.5ex~plus~1fill
4489     }{%
4490       %false
4491       % no patch
4492       \hskip-1.875ex plus-1fill
4493     }%
4494   }
4495   % Centering the bullet bar : NO
4496   % no patch
4497   \renewcommand{\gothamPatchInsertNav}{%
4498     \box\beamer@sectionbox\hfil\hskip.3cm
4499   }
4500   %% Remove hfill between sections => flush right bullet bar, if not corrected.
4501   % \patchcmd{\sectionentry}{\hskip1.875ex plus 1fill}{\hskip 3.5ex}{}{%
4502   \renewcommand{\gothamPatchSectionentry}{%
4503     \hskip~3.5ex
4504   }
4505 },
4506   mini~frames~nav~spreading / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'
4507 }

```

(End of definition for outer key - interface. This function is documented on page ??.)

outer_key-interface Controls the outer settings for mini frames navigation sectioning template.

The following test files are used for this code: gotham-test-051.

```
4508 \keys_define:nn { gotham / outer }{
4509   % mini-frames-nav-sectioning default
4510   mini-frames-nav-sectioning .choice:,
4511   mini-frames-nav-sectioning .usage:n = { general },
4512   mini-frames-nav-sectioning .default:n = { secsubsection },
4513
4514   mini-frames-nav-sectioning / none .code:n = {
4515     %
4516     \__gotham_set_template:nn{section-in-head/foot-shaded}{default/empty}
4517     \__gotham_set_template:nn{section-in-head/foot}{default/empty}
4518     \renewcommand{\gothamPatchSectionbox}{%
4519       % patch to set section box height to 0.
4520       \ht\beamer@sectionbox=0pt
4521       \dp\beamer@sectionbox=0pt
4522     }
4523   },
4524   mini-frames-nav-sectioning / section .code:n = {
4525     %
4526     \__gotham_set_template:nn{section-in-head/foot-shaded}{default} %from Beamer
4527     \__gotham_set_template:nn{section-in-head/foot}{default} %from Beamer
4528   },
4529   mini-frames-nav-sectioning / secsubsection .code:n = {
4530     %
4531     \__gotham_set_template:nn{section-in-head/foot-shaded}{default/gotham~secSubsec}
4532     \__gotham_set_template:nn{section-in-head/foot}{default/gotham~secSubsec}
4533   },
4534
4535   mini-frames-nav-sectioning / unknown .code:n = { \PackageWarning{ gotham } { The-choice-'#1
4536 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

`outer_key-interface` Controls the outer settings for mini frames navigation position template.

The following test files are used for this code: gotham-test-051.

```
4537 \tl_new:N \l__gotham_out_tmp_mfnposi_tl
4538 \tl_new:N \l__gotham_out_tmp_pbar_tl
4539 \keys_define:nn { gotham / outer }{
4540   % mini-frames-nav-position default
4541   mini-frames-nav-position .choice:,
4542   mini-frames-nav-position .usage:n = { general },
4543   mini-frames-nav-position .default:n = { none },
```

```

4544
4545   mini~frames~nav~position / none .code:n = {
4546     %
4547     % reset if it has modified by another progressbar strategy
4548     % \__gotham_set_prop_template:nn{sidebar~canvas-right/default}{#1}
4549     \tl_set:Nn \l__gotham_out_tmp_mfnposi_tl {none}
4550
4551     % head
4552     \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {
4553       % True: nothing to do it is already occupied.
4554     }{
4555       \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
4556     }
4557     % frametitle
4558     % \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
4559       % % True: nothing to do it is already occupied.
4560     }{
4561       \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
4562     }
4563     % foot
4564     \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
4565       % True: nothing to do it is already occupied.
4566     }{
4567       \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
4568     }
4569     % left
4570     \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
4571       % True: nothing to do it is already occupied.
4572     }{
4573       \setbeamertemplate{sidebar-left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar-left}]
4574     }
4575     % right
4576     \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
4577       % True: nothing to do it is already occupied.
4578     }{
4579       \setbeamertemplate{sidebar-right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar-right}]
4580     }
4581   },
4582   mini~frames~nav~position / head .code:n = {
4583     %
4584     \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
4585       % True: nothing to do it is already done.
4586     }{

```

```

4587 % False : remember that choice in order to do not apply it several time and add to beamer
4588 \tl_set:Nn \l__gotham_out_tmp_mfnposi_tl {head}
4589
4590 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {
4591   % True: nothing to do it is already occupied.
4592 }
4593   \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
4594 }
4595 % \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
4596 %   % True: nothing to do it is already occupied.
4597 }
4598 %   \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
4599 %
4600 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
4601   % True: nothing to do it is already occupied.
4602 }
4603   \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
4604 }
4605 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
4606   % True: nothing to do it is already occupied.
4607 }
4608   \setbeamertemplate{sidebar-left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar-left}]
4609 }
4610 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
4611   % True: nothing to do it is already occupied.
4612 }
4613   \setbeamertemplate{sidebar-right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar-right}]
4614 }
4615 %
4616 \addtobeamertemplate{headline}{}{
4617   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
4618     \usebeamertemplate*{mini~nav~progress~head/foot}
4619   }
4620 }
4621 }
4622 }
4623 },
4624 mini~frames~nav~position / foot .code:n = {
4625 %
4626 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
4627   % True: nothing to do it is already done.
4628 }
4629 % False : remember that choice in order to do not apply it several time and add to beamer

```

```

4630 \tl_set:Nn \l__gotham_out_tmp_mfnposi_tl {foot}
4631
4632 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {
4633   % True: nothing to do it is already occupied.
4634 }{
4635   \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
4636 }
4637 % \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
4638 %   % True: nothing to do it is already occupied.
4639 % }{
4640 %   \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
4641 % }
4642 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
4643   % True: nothing to do it is already occupied.
4644 }{
4645   \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
4646 }
4647 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
4648   % True: nothing to do it is already occupied.
4649 }{
4650   \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~left}]
4651 }
4652 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
4653   % True: nothing to do it is already occupied.
4654 }{
4655   \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~right}]
4656 }
4657
4658 \addtobeamertemplate{footline}{}{
4659   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
4660     \usebeamertemplate*{mini~nav~progress~head/foot}
4661   }{
4662   }
4663 }
4664 },
4665 mini~frames~nav~position / left .code:n = {
4666 %
4667 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
4668   % True: nothing to do it is already done.
4669 }{
4670   % False : remember that choice in order to do not apply it several time and add to beamertemplate
4671   \tl_set:Nn \l__gotham_out_tmp_mfnposi_tl {left}
4672

```

```

4673 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {
4674   % True: nothing to do it is already occupied.
4675 }{
4676   \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
4677 }
4678 \% \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
4679   % % True: nothing to do it is already occupied.
4680 }{
4681   \% \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
4682 }
4683 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
4684   % True: nothing to do it is already occupied.
4685 }{
4686   \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
4687 }
4688 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
4689   % True: nothing to do it is already occupied.
4690 }{
4691   \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~left}]
4692 }
4693 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
4694   % True: nothing to do it is already occupied.
4695 }{
4696   \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~right}]
4697 }
4698 %
4699 \addtobeamertemplate{sidebar~left}{}{
4700   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
4701     \usebeamertemplate*{mini~nav~progress~left}
4702   }{
4703   }
4704 }
4705 }
4706 },
4707 mini~frames~nav~position / right .code:n = {
4708 %
4709 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
4710   % True: nothing to do it is already done.
4711 }{
4712   % False : remember that choice in order to do not apply it several time and add to beamertemplate
4713   \tl_set:Nn \l__gotham_out_tmp_mfnposi_tl {right}
4714
4715 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {

```

```

4716     % True: nothing to do it is already occupied.
4717   }{
4718     \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
4719   }
4720   % \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
4721   % % True: nothing to do it is already occupied.
4722   % }{
4723   % \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
4724   % }
4725   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
4726   % True: nothing to do it is already occupied.
4727   }{
4728     \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
4729   }
4730   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
4731   % True: nothing to do it is already occupied.
4732   }{
4733     \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~left}]
4734   }
4735   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
4736   % True: nothing to do it is already occupied.
4737   }{
4738     \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~right}]
4739   }
4740   %
4741   \addtobeamertemplate{sidebar~right}{}{
4742     \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
4743       \usebeamertemplate*{mini~nav~progress~right}
4744     }{}
4745   }
4746 }
4747 }
4748 },
4749
4750   mini~frames~nav~position / unknown .code:n = { \PackageWarning{ gotham } { The-choice-'#1'~is~not~defined } }
4751 }

```

(End of definition for outer key - interface. This function is documented on page ??.)

Progress bar

\gothamProgressHeadFootLineheight Lengths used in tikz rectangle.

```

4752 \newlength{\gotham@progressinheadfoot}
4753 \newlength{\gothamProgressHeadFootLineheight}

```

```
4754 \setlength{\gothamProgressHeadFootLineheight}{1.2ex}
```

(End of definition for `\gothamProgressHeadFootLineheight`. This variable is documented on page 39.)

`\l_gotham_ProgCircleMoving_bool` Boolean variables controlling the direction of progression and if the current frame number
`\l_gotham_progbar_advancement_tlbr_bool` is moving with the progression and if the miniframes navigation should be printed inside
`\l_gotham_pmfn_bool` the progress bar.

```
4755 \bool_new:N \l_gotham_ProgCircleMoving_bool
4756 \bool_set_true:N \l_gotham_ProgCircleMoving_bool
4757
4758 \bool_new:N \l_gotham_progbar_advancement_tlbr_bool
4759 \bool_set_true:N \l_gotham_progbar_advancement_tlbr_bool
4760
4761 \bool_new:N \l_gotham_pmfn_bool
4762 \bool_set_false:N \l_gotham_pmfn_bool
```

(End of definition for `\l_gotham_ProgCircleMoving_bool`, `\l_gotham_progbar_advancement_tlbr_bool`,
and `\l_gotham_pmfn_bool`. These variables are documented on page 39.)

__gotham_rectangle_box_progressbar:n

#1 : width of the progress bar.

Command to draw a rectangular progress bar that can go from left to right or the opposite and that can include a navigation miniframes bar.

The following test files are used for this code: gotham-test-048.

```
4763 % #1: 'linewidth'
4764 \cs_new_protected:Npn \__gotham_rectangle_box_progressbar:n #1
4765 {
4766 %
4767 \setlength{\gotham@progressinheadfoot}{%
4768 #1 * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}}
4769 }
4770 %
4771 \begin{beamercolorbox}[wd=#1]{progress~bar~in~head/foot}
4772 \begin{tikzpicture}
4773 \usebeamercolor[progress~bar~in~head/foot]
4775 %
4776 % gray rectangle in the background.
4777 \fill[color=progress~bar~in~head/foot.bg]
4778 (0pt, 0pt) rectangle ++ (#1, \gothamProgressHeadFootLineheight)
4779 ;
4780
4781 \bool_if:NTF \l_gotham_progbar_advancement_tlbr_bool {
4782 % from left to right
4783 % orange rectangle progressing
4784 \fill[color=progress~bar~in~head/foot.fg]
4785 (0pt, 0pt) rectangle ++ (\gotham@progressinheadfoot, \gothamProgressHeadFootLineheight)
4786 ;
4787 }{
4788 % from right to left
4789 % orange rectangle progressing
4790 \fill[color=progress~bar~in~head/foot.fg]
4791 (#1, \gothamProgressHeadFootLineheight) rectangle ++ (-\gotham@progressinheadfoot, -\go
4792 ;
4793 }
4794
4795 \bool_if:NTF \l_gotham_pmfn_bool {
4796 % progress miniframes navigation is on.
4797 \node at (#1/2, \gothamProgressHeadFootLineheight/2)
4798 [text~height=0.1pt, text~depth=0.05pt, inner~sep=0pt] %draw=red,
4799 {
4800 \usebeamercolor[fg]{normal~text183}
4801 % \fontsize{3.5pt}{0pt}\selectfont
4802 \raisebox{0.5\gothamProgressHeadFootLineheight+1.4pt}[0pt][0pt]{%
4803 %\dohead
4804 \hfuzz=#1
4805 \insertnavigation{#1}
4806 }
```

progress~bar~in~head/foot}{gotham~rectangle} template displaying the progress bar in head, frametitle or footnote.

The following test files are used for this code: gotham-test-046, gotham-test-046b, gotham-test-047, gotham-test-048.

```
4816 \defbeamertemplate{progress~bar~in~head/foot}{gotham~rectangle}{
4817   \nointerlineskip
4818   \__gotham_rectangle_box_progressbar:n {\paperwidth}
4819 }
```

(End of definition for \defbeamertemplate{progress~bar~in~head/foot}{gotham~rectangle}. This function is documented on page ??.)

progress~bar~in~left/right}{gotham~rectangle} template displaying the progress bar in left or right.

The following test files are used for this code: gotham-test-046, gotham-test-046b, gotham-test-047, gotham-test-048.

```
4820 \defbeamertemplate{progress~bar~in~left}{gotham~rectangle}{
4821   \nointerlineskip
4822
4823   \settoheight{\gotham@temp@heightFrametitle}{\gotham@strut}
4824   \addtolength{\gotham@temp@heightFrametitle}{\gothamFrametitleToppadding+\gothamFrametitleBottompadding}
4825
4826   \setlength{\gotham@temp@PaperheightFrametitle}{\paperheight-\gotham@temp@heightFrametitle-\gotham@temp@heightFrametitleBottompadding}
4827
4828   \vspace{0.12275\paperheight}
4829   \rotatebox{90}{
4830     \__gotham_rectangle_box_progressbar:n {\gotham@temp@PaperheightFrametitle}
4831   }
4832 }
4833 \defbeamertemplate{progress~bar~in~right}{gotham~rectangle}{
4834   \nointerlineskip
4835
4836   \settoheight{\gotham@temp@heightFrametitle}{\gotham@strut}
4837   \addtolength{\gotham@temp@heightFrametitle}{\gothamFrametitleToppadding+\gothamFrametitleBottompadding}
4838
4839   \setlength{\gotham@temp@PaperheightFrametitle}{\paperheight-\gotham@temp@heightFrametitle-\gotham@temp@heightFrametitleBottompadding}
4840
4841   \hspace{-\gothamProgressHeadFootLineheight}
4842   \vspace{\gotham@temp@heightFrametitle-27.75pt}
4843   \rotatebox{-90}{
4844     \__gotham_rectangle_box_progressbar:n {\gotham@temp@PaperheightFrametitle}
4845   }
4846 }
```

(End of definition for \defbeamertemplate{progress-bar-in-left/right}{gotham-rectangle}. This function is documented on page ??.)

__gotham_rounded_box_progressbar:nnnn

```
#1 : width Name of the option to add, this name should also correspond to the name  
      of the environment followed by the suffix 'env'.  
#2 : ratio progressbar/extra command  
#3 : colorbox name  
#4 : extra command
```

Command to draw a rounded box progress bar that can go from left to right or the opposite and that can include a navigation miniframes bar. The fourth argument is a command to control what to display at the right side of the rounded box.

The following test files are used for this code: gotham-test-048.

```
4847 % #1: 'linewidth'  
4848 % #2: ratio of the progress bar  
4849 % #3: colorbox name  
4850 % #4: command for percent of progress  
4851 \cs_new_protected:Npn \__gotham_rounded_box_progressbar:nnnn #1#2#3#4  
4852 {  
4853   \setlength{\gotham@progressinheadfoot}{  
4854     #2#1 * \ratio{\insertframenumber pt}{\inserttotalframenumber pt}  
4855   }  
4856  
4857   % 1.035\gothamProgressHeadFootLineheight is to include the border inside the box.  
4858   \begin{beamercolorbox}[wd=#1, ht=1.035\gothamProgressHeadFootLineheight]{#3}  
4859     \hfill  
4860     \tikzexternaldisable  
4861     \begin{tikzpicture}[roundedcorners=0.5\gothamProgressHeadFootLineheight, verythin]  
4862       \usebeamercolor{progress-bar-in-head/foot}  
4863  
4864       % gray rectangle in the background.  
4865       \shade[topcolor=progress-bar-in-head/foot.bg!65, bottomcolor=progress-bar-in-head/foot.  
4866         (0pt, 0pt) rectangle ++ (#2#1, \gothamProgressHeadFootLineheight)  
4867       ;  
4868  
4869       \bool_if:NTF \l_gotham_progbar_advancement_tlbr_bool {  
4870         % from left to right  
4871         % orange rectangle progressing  
4872         \shade[draw=progress-bar-in-head/foot.fg, topcolor=progress-bar-in-head/foot.fg!70, bot  
4873           (0pt, 0pt) rectangle ++ (\gotham@progressinheadfoot, \gothamProgressHeadFootLineheight)  
4874         ;  
4875       }{  
4876         % from right to left  
4877         % orange rectangle progressing  
4878         \shade[draw=progress-bar-in-head/foot.fg, topcolor=progress-bar-in-head/foot.fg!70, bot  
4879           (#2#1, \gothamProgressHeadFootLineheight) rectangle ++ (-\gotham@progressinheadfoot, -\gothamProgressHeadFootLineheight)  
4880         ;  
4881       }  
4882  
4883       \bool_if:NTF \l_gotham_pmfn_bool {  
4884         % progress miniframes navigation is on.  
4885         \node at (#2#1/2, \gothamProgressHeadFootLineheight/2)
```

gress-bar-in-head/foot}{gotham-rounded-box} template displaying the progress bar in head, frametitle or footnote.

The following test files are used for this code: gotham-test-046, gotham-test-046b, gotham-test-047, gotham-test-048.

```
4907 \defbeamertemplate{progress-bar-in-head/foot}{gotham-rounded-box}{  
4908   \nointerlineskip  
4909   \__gotham_rounded_box_progressbar:nnnn {\paperwidth}{0.93}{footline}{  
4910     \hfill  
4911     \raisebox{0.5\gothamProgressHeadFootLineheight-1.75pt}[0pt][0pt]{  
4912       \fontsize{5pt}{0pt}\selectfont  
4913       \usebeamercolor[fg]{normal-text}  
4914       \fp_eval:n {round(\insertframenumber*100/\inserttotalframenumber,0)}\,,\%  
4915     }  
4916   }  
4917 % \__gotham_rounded_box_progressbar:nnnn {\paperwidth}{0.53}{progress-bar-in-head/foot}{  
4918 }
```

(End of definition for \defbeamertemplate{progress-bar-in-head/foot}{gotham-rounded-box}. This function is documented on page ??.)

ress-bar-in-left/right}{gotham-rounded-box} template displaying the progress bar in left or right sidebar.

The following test files are used for this code: gotham-test-046, gotham-test-046b, gotham-test-047, gotham-test-048.

```
4919 \defbeamertemplate{progress-bar-in-left}{gotham-rounded-box}{  
4920   \nointerlineskip  
4921  
4922   \settoheight{\gotham@temp@heightFrametitle}{\gotham@strut}  
4923   \addtolength{\gotham@temp@heightFrametitle}{\gothamFrametitleToppading+\gothamFrametitleBot-  
4924  
4925   \setlength{\gotham@temp@PaperheightFrametitle}{\paperheight-\gotham@temp@heightFrametitle-  
4926  
4927   \vspace{0.12275\paperheight}  
4928 % \hspace{\gothamProgressHeadFootLineheight}  
4929   \rotatebox{90}{  
4930     \__gotham_rounded_box_progressbar:nnnn {\gotham@temp@PaperheightFrametitle}{0.89}{footline}{  
4931       \hfill  
4932       \raisebox{0.5\gothamProgressHeadFootLineheight-1.75pt}[0pt][0pt]{  
4933         \fontsize{5pt}{0pt}\selectfont  
4934         \fp_eval:n {round(\insertframenumber*100/\inserttotalframenumber,0)}\,,\%  
4935       }  
4936     }  
4937 }
```

```

4938 }
4939 \defbeamertemplate{progress-bar-in-right}{gotham-rounded-box}{
4940   \nointerlineskip
4941
4942   \settoheight{\gotham@temp@heightFrametitle}{\gotham@strut}
4943   \addtolength{\gotham@temp@heightFrametitle}{\gothamFrametitleToppadding+\gothamFrametitleBot-
4944
4945   \setlength{\gotham@temp@PaperheightFrametitle}{\paperheight-\gotham@temp@heightFrametitle-\v
4946
4947   \hspace{-\gothamProgressHeadFootLineheight-0.2pt}
4948   \vspace{\gotham@temp@heightFrametitle-27.75pt}
4949   \rotatebox{-90}{
4950     \__gotham_rounded_box_progressbar:n { \gotham@temp@PaperheightFrametitle}{0.89}{footline
4951     \hfill
4952     \raisebox{0.5\gothamProgressHeadFootLineheight-1.75pt}[0pt][0pt]{
4953       \fontsize{5pt}{0pt}\selectfont
4954       \fp_eval:n {round(\insertframenumber*100/\inserttotalframenumber,0)}\%,\%
4955     }
4956   }
4957 }
4958 }

```

(End of definition for `\defbeamertemplate{progress-bar-in-left/right}{gotham-rounded-box}`. This function is documented on page ??.)

`\gothamProgressCircHeight` Lengths used in tikz rectangle.

`\gothamCounterCircleRadius`

`\gothamProgressCircBorderWidth`

```

4959 %the height of the header is 1.8 times the lineheight of the frame title
4960 \newlength{\gothamProgressCircHeight}
4961 \setlength{\gothamProgressCircHeight}{1.8\baselineskip}
4962 %\setlength{\gothamProgressCircHeight}{2\baselineskip}
4963 \newlength{\gothamCounterCircleRadius}
4964 \setlength{\gothamCounterCircleRadius}{1.12ex}
4965 % width of the border
4966 \newlength{\gothamProgressCircBorderWidth}
4967 \setlength{\gothamProgressCircBorderWidth}{1.65mm}
4968
4969 %% Induced length used internally, but can still be tuned manually by inspired people.
4970 % radius of the logo
4971 \newlength{\gothamProgressCircLogoRadius}
4972 \setlength{\gothamProgressCircLogoRadius}{1.2\gothamProgressCircHeight/2}
4973 % inner radius of border of the logo frame
4974 \newlength{\gothamProgressCircLogoInnerRadius}
4975 \setlength{\gothamProgressCircLogoInnerRadius}{1.1\gothamProgressCircLogoRadius}

```

```

4976 % radius of the outer border of the logo frame
4977 \newlength{\gothamProgressCircLogoOuterRadius}
4978 \setlength{\gothamProgressCircLogoOuterRadius}{\gothamProgressCircLogoInnerRadius+\gothamPro
4979 % radius of the counters
4980 \newlength{\gothamCounterRadius}
4981 \setlength{\gothamCounterRadius}{\gothamProgressCircLogoInnerRadius/2+\gothamProgressCircLog

```

(End of definition for `\gothamProgressCircHeight`, `\gothamCounterCircleRadius`, and `\gothamProgressCircBorderWidth`.
These variables are documented on page 39.)

`\l_gotham_ratio_progresscircle_fp` angle ratio of the progress in degree and angle of the counter circle intercepted by the
`\l_gotham_angle_counterradius_fp` half of the border.

```

4982 % \fp_new:N \l_gotham_ratio_progress_fp
4983 \fp_new:N \l_gotham_ratio_progresscircle_fp
4984 % the angle token by the counter radius
4985 \fp_new:N \l_gotham_angle_counterradius_fp
4986 % requires xfp for asind
4987 \fp_set:Nn \l_gotham_angle_counterradius_fp {
4988   \fpeval{ 2* asind (\gothamCounterCircleRadius / (2*\gothamCounterRadius)) }
4989 }

```

(End of definition for `\l_gotham_ratio_progresscircle_fp` and `\l_gotham_angle_counterradius_fp`.
These variables are documented on page ??.)

`\gothamInstituteLogoCircle[#1]`

#1 : height of the picture

Command to be redefined by users.

The following test files are used for this code: gotham-test-046b.

```

4990 \providecommand{\gothamInstituteLogoCircle}[1][4ex]{
4991   \includegraphics[height=#1]{gotham-logo.pdf}
4992 }

```

`\gothamProgressCircle` Internal command plotting the circle progress and that is used internal in the instituteLogo template within the frametitle template.

The following test files are used for this code: gotham-test-046b.

```
4993 \providecommand{\gothamProgressCircle}{%
4994 % \tikzexternaldisable
4995 \begin{tikzpicture}[remember picture, overlay]
4996 % Load colors
4997 \usebeamercolor{standin}
4998 \usebeamercolor{frametitle}
4999 \usebeamercolor{progress-bar-in-head/foot}
5000
5001 % Define center
5002 \coordinate (localCenter);
5003 % draw the outer circle
5004 \fill[fill=progress-bar-in-head/foot.bg] (localCenter) circle (\gothamProgressCircLogoRadius);
5005 % draw the inner circle
5006 \fill[fill=frametitle.bg] (localCenter) circle (\gothamProgressCircLogoInnerRadius);
5007 \node at (localCenter) {\gothamInstituteLogoCircle[1.9\gothamProgressCircLogoRadius]};
5008
5009 %% draw progress circle/bar
5010 \bool_if:NTF \l_gotham_ProgCircleMoving_bool {
5011 % the circular counter with a moving counter
5012
5013 %% compute the angle for the progress circle
5014 \bool_if:NTF \l_gotham_progbar_advancement_tlbr_bool {
5015   \fp_set:Nn \l_gotham_ratio_progresscircle_fp {-(360)*\insertframenumber/\inserttotalframes}
5016 }{
5017   \%else% clockwise rotation
5018   \fp_set:Nn \l_gotham_ratio_progresscircle_fp {(360)*(\insertframenumber/\inserttotalframes)}
5019 }
5020 \%fi
5021
5022 % draw the arc progress bar
5023 \draw[
5024   color=progress-bar-in-head/foot.fg,
5025   line-width=0.6*\gothamProgressCircBorderWidth
5026 ]
5027   (localCenter)
5028   ++
5029   ([
5030     xshift=\gothamCounterRadius
5031   ]localCenter)
5032   arc[
5033     radius=\gothamCounterRadius,    190
5034     start-angle=0,
5035     end-angle={\fp_eval:n \l_gotham_ratio_progresscircle_fp}
5036   ]
5037   ;
5038
5039 % draw a point at the beginning of the progress circle
```

`outer_key_interface` Controls the outer settings for progress bar.

The following test files are used for this code: gotham-test-048.

```
5149 % token list to remember what is the current state
5150 % \tl_new:N \l__gotham_out_tmp_pbar_tl
5151 \keys_define:nn { gotham / outer }{
5152   % progressbar~position default
5153   progressbar~position .choice:,
5154   progressbar~position .usage:n = { general },
5155   progressbar~position .default:n = { none },
5156
5157   progressbar~position / none .code:n = {
5158     % reset if it has modified by another progressbar~position strategy
5159     % \__gotham_set_prop_template:nn{sidebar~canvas-right/default}{#1}
5160     \tl_set:Nn \l__gotham_out_tmp_pbar_tl {none}
5161
5162     % head
5163     \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5164       % True: nothing to do it is already occupied.
5165     }{
5166       \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
5167     }
5168     % frametitle
5169     % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5170     % % True: nothing to do it is already occupied.
5171     % }{
5172       \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
5173     %
5174     % foot
5175     \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5176       % True: nothing to do it is already occupied.
5177     }{
5178       \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
5179     }
5180     % left
5181     \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5182       % True: nothing to do it is already occupied.
5183     }{
5184       \setbeamertemplate{sidebar-left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar-left}]
5185     }
5186     % right
5187     \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5188       % True: nothing to do it is already occupied.
```

```

5189  }{
5190   \setbeamertemplate{sidebar-right}[default]{\prop_item:Nn \l__gotham_template_name_prop {si
5191 }
5192
5193 % logo
5194 \__gotham_set_prop_template:nn{includeLogo/default}{gotham-square}
5195 % section in head
5196 \setbeamertemplate{section-in-head/foot-shaded}[default]{\prop_item:Nn \l__gotham_template_
5197 \setbeamertemplate{section-in-head/foot}[default]{\prop_item:Nn \l__gotham_template_name_pr
5198 },
5199 progressbar-position / head .code:n = {
5200 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {
5201 % True: nothing to do it is already done.
5202 } {
5203 % False : remember that choice in order to do not apply it several time and add to beamer
5204 \tl_set:Nn \l__gotham_out_tmp_pbar_tl {head}
5205
5206 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5207 % True: nothing to do it is already occupied.
5208 }{
5209 \setbeamertemplate{headline}[default]{\prop_item:Nn \l__gotham_template_name_prop {headli
5210 }
5211 % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5212 % % True: nothing to do it is already occupied.
5213 % }{
5214 \setbeamertemplate{frametitle}[default]{\prop_item:Nn \l__gotham_template_name_prop {fram
5215 %
5216 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5217 % True: nothing to do it is already occupied.
5218 }{
5219 \setbeamertemplate{footline}[default]{\prop_item:Nn \l__gotham_template_name_prop {footli
5220 }
5221 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5222 % True: nothing to do it is already occupied.
5223 }{
5224 \setbeamertemplate{sidebar-left}[default]{\prop_item:Nn \l__gotham_template_name_prop {si
5225 }
5226 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5227 % True: nothing to do it is already occupied.
5228 }{
5229 \setbeamertemplate{sidebar-right}[default]{\prop_item:Nn \l__gotham_template_name_prop {si
5230 }
5231

```

```

5232 %
5233 \addtobeamertemplate{headline}{}{
5234   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {head} {
5235     \usebeamertemplate*{progress~bar~in~head/foot}
5236   }{}
5237 }
5238 }
5239 },
5240 progressbar~position / frametitle .code:n = {
5241   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
5242     % True: nothing to do it is already done.
5243   }{
5244     % False : remember that choice in order to do not apply it several time and add to beamertemplate
5245   \tl_set:Nn \l__gotham_out_tmp_pbar_tl {frametitle}
5246
5247   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5248     % True: nothing to do it is already occupied.
5249   }{
5250     \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
5251   }
5252   % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5253   % % True: nothing to do it is already occupied.
5254   % }{
5255   \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
5256   %
5257   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5258     % True: nothing to do it is already occupied.
5259   }{
5260     \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
5261   }
5262   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5263     % True: nothing to do it is already occupied.
5264   }{
5265     \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~left}]
5266   }
5267   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5268     % True: nothing to do it is already occupied.
5269   }{
5270     \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~right}]
5271   }
5272
5273 %
5274 \addtobeamertemplate{frametitle}{}{

```

```

5275   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {frametitle} {
5276     \usebeamertemplate*{progressbar~bar~in~head/foot}
5277   }{}
5278 }
5279 }
5280 },
5281 progressbar~position / foot .code:n = {
5282   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
5283     % True: nothing to do it is already done.
5284   } {
5285     % False : remember that choice in order to do not apply it several time and add to beamertem
5286     \tl_set:Nn \l__gotham_out_tmp_pbar_tl {footline}
5287
5288   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5289     % True: nothing to do it is already occupied.
5290   }{
5291     \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headli
5292   }
5293   % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5294   % % True: nothing to do it is already occupied.
5295   % }{
5296     \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {fram
5297   }
5298   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5299     % True: nothing to do it is already occupied.
5300   }{
5301     \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footli
5302   }
5303   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5304     % True: nothing to do it is already occupied.
5305   }{
5306     \setbeamertemplate{sidebar-left}[default/\prop_item:Nn \l__gotham_template_name_prop {si
5307   }
5308   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5309     % True: nothing to do it is already occupied.
5310   }{
5311     \setbeamertemplate{sidebar-right}[default/\prop_item:Nn \l__gotham_template_name_prop {si
5312   }
5313
5314 %
5315 \addtobeamertemplate{footline}{}{
5316   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {footline} {
5317     \usebeamertemplate*{progressbar~bar~in~head/foot}

```

```

5318     }{}
5319   }
5320 }
5321 },
5322 progressbar~position / circlehead .code:n = {
5323   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {circlehead} {
5324     % True: nothing to do it is already done.
5325   } {
5326     % False : remember that choice in order to do not apply it several time and add to beamer
5327     \tl_set:Nn \l__gotham_out_tmp_pbar_tl {circlehead}
5328
5329 %
5330 %%%\prop_put:Nnn \l__gotham_template_name_SAVE_prop {includeLogo/default} {gotham~square}
5331 \__gotham_set_prop_template:nn{includeLogo/default}{gotham~circle}
5332 \__gotham_set_template:nn{section~in~head/foot~shaded}{default/gotham~secSubsec}
5333 \__gotham_set_template:nn{section~in~head/foot}{default/gotham~secSubsec}
5334 % \__gotham_set_template:nn{headline}{default/gotham~section}
5335 % \setbeamertemplate{headline}[default/gotham~section]
5336
5337 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5338   % True: it is already occupied, so let's emulate the gotham section
5339   \addtobeamertemplate{headline}{}{
5340     \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {circlehead} {
5341       \begin{beamercolorbox}[wd=1.0\paperwidth, ht=2.5ex, dp=1.4ex, left]{headfoot}
5342         \usebeamertemplate{section~in~head/foot}\hspace*{3.5ex}
5343         \usebeamertemplate{section~in~head/foot}
5344       \end{beamercolorbox}
5345     }{}
5346   }
5347 }{
5348   % \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {head}
5349   \__gotham_set_template:nn{headline}{default/gotham~section}
5350 }
5351 % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5352 %   % True: nothing to do it is already occupied.
5353 % }{
5354   \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {fram
5355   % }
5356   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5357     % True: nothing to do it is already occupied.
5358   }{
5359     \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footli
5360   }

```

```

5361 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5362   % True: nothing to do it is already occupied.
5363 }{
5364   \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {si
5365 }
5366 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5367   % True: nothing to do it is already occupied.
5368 }{
5369   \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {si
5370 }
5371 }
5372 },
5373 progressbar~position / left .code:n = {
5374 \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
5375   % True: nothing to do it is already done.
5376 } {
5377   % False : remember that choice in order to do not apply it several time and add to beamer
5378 \tl_set:Nn \l__gotham_out_tmp_pbar_tl {left}
5379
5380 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5381   % True: nothing to do it is already occupied.
5382 }{
5383   \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headli
5384 }
5385 % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5386 %   % True: nothing to do it is already occupied.
5387 % }{
5388   \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {fram
5389 % }
5390 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5391   % True: nothing to do it is already occupied.
5392 }{
5393   \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footli
5394 }
5395 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5396   % True: nothing to do it is already occupied.
5397 }{
5398   \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {si
5399 }
5400 \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5401   % True: nothing to do it is already occupied.
5402 }{
5403   \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {si

```

```

5404 }
5405 %
5406 \addtobeamertemplate{sidebar~left}{}{
5407   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {left} {
5408     \usebeamertemplate*{progress~bar-in~left}
5409   }{}
5410 }
5411 }
5412 }
5413 },
5414 progressbar~position / right .code:n = {
5415   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
5416     % True: nothing to do it is already done.
5417   } {
5418     % False : remember that choice in order to do not apply it several time and add to beamer
5419     \tl_set:Nn \l__gotham_out_tmp_pbar_tl {right}
5420
5421   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {head} {
5422     % True: nothing to do it is already occupied.
5423   }{
5424     \setbeamertemplate{headline}[default/\prop_item:Nn \l__gotham_template_name_prop {headline}]
5425   }
5426   % \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {frametitle} {
5427   % % True: nothing to do it is already occupied.
5428   % }{
5429     \setbeamertemplate{frametitle}[default/\prop_item:Nn \l__gotham_template_name_prop {frametitle}]
5430   %
5431   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {foot} {
5432     % True: nothing to do it is already occupied.
5433   }{
5434     \setbeamertemplate{footline}[default/\prop_item:Nn \l__gotham_template_name_prop {footline}]
5435   }
5436   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {left} {
5437     % True: nothing to do it is already occupied.
5438   }{
5439     \setbeamertemplate{sidebar~left}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~left}]
5440   }
5441   \tl_if_eq:VnTF \l__gotham_out_tmp_mfnposi_tl {right} {
5442     % True: nothing to do it is already occupied.
5443   }{
5444     \setbeamertemplate{sidebar~right}[default/\prop_item:Nn \l__gotham_template_name_prop {sidebar~right}]
5445   }

```

```

5447 %
5448 \addtobeamertemplate{sidebar-right}{}{
5449   \tl_if_eq:VnTF \l__gotham_out_tmp_pbar_tl {right} {
5450     \usebeamertemplate*{progress-bar-in-right}
5451   }{}
5452 }
5453 }
5454 },
5455
5456 progressbar~position / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~u
5457 }

```

(End of definition for outer key - interface. This function is documented on page ??.)

`outer_key_-_interface` Controls the outer settings for progress bar style.

The following test files are used for this code: `gotham-test-049`.

```

5458 % token list to remember what is the current state
5459 \keys_define:nn { gotham / outer }{
5460   % progressbar-style default
5461   progressbar-style .choice:,,
5462   progressbar-style .usage:n = { general },
5463   progressbar-style .default:n = { rectangle },
5464
5465   progressbar-style / rectangle .code:n = {
5466     %
5467     % \defbeamertemplate*{progress-bar-in-head/foot}{gotham-rectangle}
5468     \__gotham_set_template:nn{progress-bar-in-head/foot}{gotham-rectangle}
5469     \__gotham_set_template:nn{progress-bar-in-left}{gotham-rectangle}
5470     \__gotham_set_template:nn{progress-bar-in-right}{gotham-rectangle}
5471   },
5472
5473   progressbar-style / rounded-box .code:n = {
5474     %
5475     \__gotham_set_template:nn{progress-bar-in-head/foot}{gotham-rounded-box}
5476     \__gotham_set_template:nn{progress-bar-in-left}{gotham-rounded-box}
5477     \__gotham_set_template:nn{progress-bar-in-right}{gotham-rounded-box}
5478   },
5479
5480   progressbar-style / moving-circle .code:n = {
5481     %
5482     \bool_set_true:N \l_gotham_ProgCircleMoving_bool
5483   },
5484

```

```

5485 progressbar~style / fixed-circle .code:n = {
5486   %
5487   \bool_set_false:N \l_gotham_ProgCircleMoving_bool
5488 },
5489
5490 progressbar~style / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~unkn
5491 }

```

(End of definition for outer key - interface. This function is documented on page ??.)

outer_key_-_interface Controls the outer settings for progress bar style.

The following test files are used for this code: gotham-test-049.

```

5492 % token list to remember what is the current state
5493 \keys_define:nn { gotham / outer }{
5494   % progressbar~advancement default
5495   progressbar~advancement .choice:,,
5496   progressbar~advancement .usage:n = { general },
5497   progressbar~advancement .default:n = { tlbr },
5498
5499   progressbar~advancement / tlbr .code:n = {
5500     %
5501     \bool_set_true:N \l_gotham_progbar_advancement_tlbr_bool
5502   },
5503   progressbar~advancement / TLBR .code:n = {
5504     %
5505     \bool_set_true:N \l_gotham_progbar_advancement_tlbr_bool
5506   },
5507
5508   progressbar~advancement / brlt .code:n = {
5509     %
5510     \bool_set_false:N \l_gotham_progbar_advancement_tlbr_bool
5511   },
5512   progressbar~advancement / BRLT .code:n = {
5513     %
5514     \bool_set_false:N \l_gotham_progbar_advancement_tlbr_bool
5515   },
5516
5517   progressbar~advancement / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~unkn
5518 }

```

(End of definition for outer key - interface. This function is documented on page ??.)

outer_key_-_interface Controls the outer settings for progress bar style.

The following test files are used for this code: gotham-test-049.

```
5519 % token list to remember what is the current state
5520 \keys_define:nn { gotham / outer }{
5521   % progressbar-mfn default
5522   progressbar-mfn .choice:,
5523   progressbar-mfn .usage:n = { general },
5524   progressbar-mfn .default:n = { off },
5525
5526   progressbar-mfn / true .code:n = {
5527     \bool_set_true:N \l_gotham_pmf_n_bool
5528
5529     \__gotham_set_template:nn{section-in-head/foot-shaded}{default/empty}
5530     \__gotham_set_template:nn{section-in-head/foot}{default/empty}
5531     \renewcommand{\gothamPatchSectionbox}{
5532       % patch to set section box height to 0.
5533       \ht\beamer@sectionbox=0.ex
5534       \dp\beamer@sectionbox=0.ex
5535     }
5536   },
5537   progressbar-mfn / on .code:n = {
5538     \bool_set_true:N \l_gotham_pmf_n_bool
5539
5540     \__gotham_set_template:nn{section-in-head/foot-shaded}{default/empty}
5541     \__gotham_set_template:nn{section-in-head/foot}{default/empty}
5542     \renewcommand{\gothamPatchSectionbox}{
5543       % patch to set section box height to 0.
5544       \ht\beamer@sectionbox=0.ex
5545       \dp\beamer@sectionbox=0.ex
5546     }
5547   },
5548   progressbar-mfn / enable .code:n = {
5549     \bool_set_true:N \l_gotham_pmf_n_bool
5550
5551     \__gotham_set_template:nn{section-in-head/foot-shaded}{default/empty}
5552     \__gotham_set_template:nn{section-in-head/foot}{default/empty}
5553     \renewcommand{\gothamPatchSectionbox}{
5554       % patch to set section box height to 0.
5555       \ht\beamer@sectionbox=0.ex
5556       \dp\beamer@sectionbox=0.ex
5557     }
5558   },
5559
5560   progressbar-mfn / false .code:n = { \bool_set_false:N \l_gotham_pmf_n_bool },
```

```

5561   progressbar~mfn / off .code:n = { \bool_set_false:N \l_gotham_pmf_n_bool },
5562   progressbar~mfn / disable .code:n = { \bool_set_false:N \l_gotham_pmf_n_bool },
5563
5564   progressbar~mfn / unknown .code:n = { \PackageWarning{ gotham } { The~choice~'#1'~is~unknown }
5565 }
```

(End of definition for outer key - interface. This function is documented on page ??.)

`Default_outer_keys` Apply default key options.

The following test files are used for this code: *gotham-test-048*.

```

5566 % when no value is given, default is called.
5567 \keys_set:nn { gotham / outer } {
5568   sidebar~canvas~right~template, sidebar~canvas~left~template,
5569   edging~default,
5570   frametitle~template, framesubtitle~template, frametitle~continuation~template,
5571   numbering,
5572   rotateFooter~default,
5573   footer~template,
5574   mini~frames~shape, mini~frames~bundle,
5575   mini~frames~compress,
5576   mini~frames~nav~spreading,
5577   mini~frames~nav~sectioning,
5578   mini~frames~nav~position,
5579   progressbar~position, progressbar~style, progressbar~advancement, progressbar~mfn,
5580 }
```

(End of definition for Default_outer_keys. This function is documented on page ??.)

`Process_outer_keys` Process package options.

The following test files are used for this code: *gotham-test-048*.

```

5581 \ProcessKeyOptions[ gotham / outer ]
5582 % \mode<all>
```

(End of definition for Process_outer_keys. This function is documented on page ??.)

```

5583 %\endinput
5584 </outer>
```

```

5585 <*package>
5586 \RequirePackage{expl3}
5587 \RequirePackage{xparse}
```

```

5588 % \RequirePackage{ifxetex}
5589 % \RequirePackage{ifluatex}
5590 % \RequirePackage{etoolbox}
5591 % \RequirePackage{xcolor}
5592 % \RequirePackage{tikz}
5593 % \RequirePackage{calc} % I think I can remove it with a bit of work
5594 % \RequirePackage{xfp}

5595 %%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%
5596 %% PACKAGE %%%
5597 %%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%
5598 %
5599 %

```

Most options are passed off to the component sub-packages.

```

5600 %
5601 %
5602 \usefonttheme{gotham}
5603 \usecolortheme{gotham}
5604 \useinnertheme{gotham}
5605 \useoutertheme{gotham}
5606 %
5607 %
5608 %
5609
5610 %%%% Setting keys %%%%
5611
5612 % set new counter for how many time the lookup is used
5613 \int_new:N \l_gotham_lookup_cnt
5614 \int_set:Nn \l_gotham_lookup_cnt {0}
5615
5616 \seq_const_from_clist:Nn \c__gotham_load_submodules_seq { font, color, inner, outer }
5617
5618 \cs_new_protected:Npn \__gotham_lookup_keymodules:nn #1#2
5619 {
5620   \int_incr:N \l_gotham_lookup_cnt
5621   % \int_show:n \l_gotham_lookup_cnt
5622
5623   % if lookup counter is lower than the number of submodules-1 [before it was +1, not complete]
5624   \if_int_compare:w \l_gotham_lookup_cnt < 2
5625     %true : do nothing
5626   \else:
5627     % \int_show:n \l_gotham_lookup_cnt

```

```

5628 \seq_map_inline:Nn \c__gotham_load_submodules_seq
5629 {
5630   \keys_if_exist:nNT { gotham / ##1 } {#1}
5631   {
5632     % missing feature in 13keys, we have no better way to detect an omitted value, so we hav
5633     \tl_if_empty:nTF {#2}
5634     { \keys_set:nn { gotham / ##1 } { #1 } }
5635     { \keys_set:nn { gotham / ##1 } { #1 = {#2} } }
5636     \prg_break:
5637   }
5638 }
5639 \msg_error:nnn { gotham } { unknown-key } {#1}
5640 \prg_break_point:
5641 \fi:
5642 }
5643 \cs_generate_variant:Nn \__gotham_lookup_keymodules:nn { Vn }
5644 \msg_new:nnn { gotham } { unknown-key } { Unknown~ key~ #1~ encountered. }
5645
5646 % Property list for all groups.
5647 \prop_new:N \l__gotham_all_all_user_keys_prop
5648 \prop_const_from_keyval:Nn \c__gotham_all_pkg_keys_prop {}
5649
5650 \keys_define:nn { gotham / all / all }
5651 {
5652   unknown .code:n =
5653   {\__gotham_lookup_keymodules:Vn \l_keys_key_str {#1}}
5654 }
5655
5656 % Set default keys/options from keyval
5657 % \__gotham_set_default_from_keyval: variant, keyval, group command
5658 \cs_new_protected:Npn \__gotham_set_default_from_keyval:nnn #1 #2 #3
5659 { %%
5660   % Check if keyvalues have been given.
5661   \tl_if_novalue:nTF {#2}
5662   { % no user keys given so _user_keys_prop is taking pkg prop
5663     \prop_set_eq:cc { l__gotham_#3_#1_user_keys_prop } { c__gotham_#3_pkg_keys_prop }
5664   }% user key given and put it in prop
5665   \prop_put_from_keyval:cn { l__gotham_#3_#1_user_keys_prop } {#2}
5666 }% end if
5667 %
5668 % xx
5669 \__gotham_set_default_auxi:cnn { l__gotham_#3_#1_user_keys_prop } {#1} {#3}
5670 %

```

```

5671  % xx
5672  \keys_set:nn { gotham/#3/#1 } { default }
5673 }
5674 %
5675 % prop-key-val, variant, group command
5676 \cs_new_protected:Npn \__gotham_set_default_auxi:Nnn #1 #2 #3
5677 {
5678   \__gotham_set_default_auxii:fnn { \prop_to_keyval:N #1 } {#2} {#3}
5679 }
5680 \cs_generate_variant:Nn \__gotham_set_default_auxi:Nnn { c }
5681 %
5682 % key-val, variant, group command
5683 \cs_new_protected:Npn \__gotham_set_default_auxii:nnn #1 #2 #3
5684 {
5685   \keys_define:nn { gotham/#3/#2 } { default .meta:n = {#1} }
5686 }
5687 \cs_generate_variant:Nn \__gotham_set_default_auxii:nnn { f }
5688 %
5689 %
5690 % (re)set keys/options by default for a group of commands.
5691 % \gothamset m:options:#1
5692 \DeclareDocumentCommand{\gothamset}{m}
5693 {
5694   \__gotham_set_default_from_keyval:nnn { all } {#1} { all }
5695   \keys_set:nn { gotham/all/all } { default }
5696 }
5697
5698 \def\gotham@plaintitleformat#1{#1}
5699 \providecommand{\mreducelistspacing}{\vspace{-\topsep}}
5700
5701 \ProcessOptionsBeamer
5702 \keys_define:nn { gotham / font }
5703 {
5704   unknown .code:n =
5705     {\__gotham_lookup_keymodules:Vn \l_keys_key_str {#1}}
5706 }
5707 \keys_define:nn { gotham / color }
5708 {
5709   unknown .code:n =
5710     {\__gotham_lookup_keymodules:Vn \l_keys_key_str {#1}}
5711 }
5712 \keys_define:nn { gotham / inner }
5713 {

```

```
5714 unknown .code:n =
5715   {\_\_gotham\_lookup\_keymodules:Vn \l_keys_key_str {#1}}
5716 }
5717 \keys_define:nn { gotham / outer }
5718 {
5719   unknown .code:n =
5720   {\_\_gotham\_lookup\_keymodules:Vn \l_keys_key_str {#1}}
5721 }
5722
5723 \ProcessKeyOptions[ gotham / font ]
5724 \ProcessKeyOptions[ gotham / color ]
5725 \ProcessKeyOptions[ gotham / inner ]
5726 \ProcessKeyOptions[ gotham / outer ]
5727
5728 %
5729 %\endinput
5730 </package>
```

Change History

v0.2.0
font_messages: New 41